

AKiPS™

Network Monitoring Software

API reference guide



© 2021 AKIPS Holdings Pty Ltd

All rights reserved worldwide. No part of this document may be reproduced by any means, nor modified, decompiled, disassembled, published or distributed, in whole or in part, or translated to any electronic medium or other means, without the written consent of AKIPS Holdings Pty Ltd.

All rights, title and interest in and to the software documentation are and shall remain the exclusive property of AKIPS and its licensors.

All other trademarks contained in this document are the property of their respective owners.

Disclaimer

While the publisher (AKIPS Pty Ltd) has taken every precaution in the preparation of this guide to ensure that the information and instructions contained herein are accurate at the date of publication, it makes no expressed or implied warranty of any kind, and disclaims all responsibility for errors or omissions. The publisher assumes no liability for incidental or consequential losses or damages in connection with, or arising out of, the use of the information contained herein.

Publisher

AKIPS, PO Box 3422, Shailer Park, Queensland, 4128, Australia

Email: info@akips.com

Website: <https://www.akips.com>

Edition	Software release	Date
16	22.1	January 2022

Contents

1	About this guide	6
1.1	Abbreviations	7
1.2	Text conventions	10
1.3	Syntax	11
2	AKIPS API	12
2.1	Test environment	12
2.2	Command console	13
2.3	Regex	14
2.4	Time filters	15
2.4.1	tf pairs and tf span	19
2.4.2	tf check	22
2.5	IP address filters	23
3	Database overview	25
3.1	Entities	25
3.1.1	Level 1: parent	27
3.1.2	Level 2: child	27
3.1.3	Level 3: attribute	28
3.1.4	Virtual attributes	29
3.2	Groups	30
3.2.1	Super groups	31
3.2.2	Configuring groups	34
3.3	Events records	41
3.4	Time series	42

<i>CONTENTS</i>	3
4 Config and events	43
4.1 Entity commands	43
4.1.1 add	43
4.1.2 delete	46
4.1.3 get	47
4.1.4 mdelete	49
4.1.5 mget	50
4.1.6 mlist	53
4.1.7 mtype	55
4.1.8 rename	56
4.1.9 set	57
4.2 Group commands	58
4.2.1 add	58
4.2.2 assign	60
4.2.3 clear	65
4.2.4 count	66
4.2.5 delete	67
4.2.6 get	68
4.2.7 list	69
4.2.8 mget	71
4.2.9 mlist	71
4.2.10 mtype	72
4.2.11 prune	72
4.2.12 rename	73
4.3 Event commands	74
4.3.1 add	75
4.3.2 clear	76
4.3.3 delete	76
4.3.4 mdelete	77
4.3.5 mget	78
4.3.6 set	80
4.3.7 tget	81

<i>CONTENTS</i>	4
4.4 Time-series commands	82
4.4.1 calc	82
4.4.2 mcalc	83
4.4.3 mget	84
4.4.4 series	85
4.4.5 top	86
4.5 Web API	87
4.5.1 cURL	90
4.5.2 data	91
5 Syslog and traps reporter	92
5.1 CSV output	93
5.2 Web API	96
6 Availability	98
6.1 Group	99
6.2 Device	100
6.3 Events	101
7 NetFlow reporter	102
7.1 CSV output	105
7.2 Web API	106
8 NetFlow time series	109
8.1 CSV output	110
8.2 Web API	111
9 Switch port mapper	114
9.1 CSV output	115
9.2 Web API	116
10 Unused interfaces	118
10.1 CSV output	118
10.2 Web API	119

11 TCP socket	121
12 Perl modules	122
12.1 Common	122
12.1.1 Useful arrays	123
12.1.2 PRINT_LINE	124
12.1.3 trim	124
12.1.4 errlog	125
12.1.5 get_localtime()	126
12.1.6 mail()	127
12.1.7 syslog()	128
12.1.8 http_send() and http_result()	129
12.2 AKIPS database	130
12.2.1 adb_send()	130
12.2.2 adb_flush()	130
12.2.3 adb_result()	130
12.3 Discover	131
12.3.1 discover_scan()	131
12.3.2 discover_config()	132
12.3.3 discover_device_rewalk()	132
13 Site scripts	133
13.1 Using site scripts	134
13.2 Naming a site script	137
13.3 Alerting site scripts	138

Chapter 1

About this guide

The AKIPS *API reference guide* assists users of API code in AKIPS Network Monitoring Software.

The following **Abbreviations** (see 1.1), **Text conventions** (see 1.2) and **Syntax** (see 1.3) are used throughout AKIPS's guides.

1.1 Abbreviations

3DES	triple data encryption standard
ADB	AKIPS database
AES	advanced encryption standard
AKIPS	Always Keep It Purely Simple :)
API	application programming interface
ARP	address resolution protocol
AS	autonomous system
BFD	bidirectional forwarding detection
BGP	border gateway protocol
CA	certificate authority
CBQoS	class-based quality of service
CDP	Cisco discovery protocol
CGI	computer gateway interface
CIDR	classless inter-domain routing
CLI	command line interface
CPU	central processing unit
CSR	certificate signing request
CSV	comma-separated values
cURL	client url
DHCP	dynamic host configuration protocol
DN	distinguished name
DNS	domain name system
FQDN	fully qualified domain name
GB	gigabyte
GRE	generic routing encapsulation
GUI	graphical user interface
HTTP	hypertext transfer protocol
HTTPS	hypertext transfer protocol secure
IF-MIB	interface MIB
IP	internet protocol
IPFIX	internet protocol flow information export
IPSLA	internet protocol service level agreement
IS-IS	intermediate system to intermediate system

LAN	local area network
LDAP	lightweight directory access protocol
LLDP	link layer discovery protocol
MAC	media access control
MIB	management information base
NAS	network-attached storage
NDP	neighbour discovery protocol
NIC	network interface card
NMS	network-monitoring software
NTP	network time protocol
OID	object identifier
OS	operating system
PCRE	Perl-compatible regular expressions
PEM	privacy-enhanced mail
PFX	personal information exchange format
PKCS	public key cryptography standards
png	portable network graphics
POSIX	portable operating system interface
PSSH	parallel secure shell
QoS	quality of service
RADIUS	remote authentication dial-in user service
RAID	redundant array of independent disks
RAM	random-access memory
RTT	round-trip time
SAN	storage area network
SCSI	small computer system interface
SHA	secure hash algorithm
SMI	structure of management information
SMTP	simple mail transfer protocol
SNMP	simple network management protocol
SSH	secure shell
SSL	secure sockets layer
STARTTLS	start transport layer security
stderr	standard error
sysadmin	system administrator

TACACS+	terminal access controller access-control system plus
TCP	transmission control protocol
TLS	transport layer security
TOS	type of service
UID	user identifier
UDP	user datagram protocol
UTC	coordinated universal time
VLAN	virtual local area network
VM	virtual machine
WAN	wide area network

1.2 Text conventions

Menu options are in **bold**.

E.g. **Go to Admin > System > System Settings**

Bold is also used for emphasis or clarity.

E.g. The **backup server** must have double the disk space of the **production server**.

Links to other parts of this guide are shown as **red** boxes.

E.g. The following **Abbreviations** (see 1.1), **Text conventions** (see 1.2) and **Syntax** (see 1.3) are used throughout AKIPS's guides.

Websites and email addresses are in **blue**.

If they are also hyperlinks, they are shown as **cyan** boxes.

E.g. <https://www.akips.com>

Code is in **monospace**.

Further:

Command syntax is in **red monospace**.

E.g. `{ddd} {hh:mm} to {hh:mm}`

Input (by the user) is in **blue monospace**.

E.g. `tf dump last7d`

Output (by AKIPS) is in **cyan monospace**.

E.g. `cisco-74-1-1 sys ip4addr = 10.74.1.1`

1.3 Syntax

Syntax may be presented in this guide across multiple lines due to layout constraints. When using AKIPS, you will need to run commands in a single line.

Parameters (fields expecting a substituted value) are contained within { } (braces).

E.g. `{type} {value}`

Optional parameters are contained within [] (square brackets).

E.g. `[index,{description}]`

Optional parameters may be nested.

E.g.

`mlist {type} [{parent regex} [{child regex} [{attribute regex}]]]`

For values separated by a | (pipe), choose one option only.

E.g. `[any|all|not group {group name} ...]`

Multiple parameters will have an ... (ellipsis).

E.g. `not group {group name} ...`

Chapter 2

AKIPS API

2.1 Test environment

AKIPS recommends that you test all API code in a test environment.

Email keys@akips.com to request a licence.

Refer to the 'AKIPS licence' chapter in the AKIPS *Install & upgrade guide*.

To view the video *AKIPS licence*,
visit <https://vimeo.com/manage/videos/514080623>

Before you execute code in your production environment, ensure that you have a current backup.

Refer to the AKIPS *Backup & restore guide*.

2.2 Command console

Warning: for expert use only.

Only admin users may access the command console.

To use the command console:

Go to **Admin > API > Command Console**.

To run commands:

In the text field, enter your command/s.

Click **Run Commands**.

To view your command history:

Click **History**.

2.3 Regex

Regex syntax depends on its underlying language (C, Perl, Java, JavaScript, Python, etc), which is responsible for compiling and executing the expression.

AKIPS is written in C and Perl, with a small amount of JavaScript.

All of our C programs are compatible with the PCRE library.

AKIPS API requires that:

- all regex strings be enclosed within / / (forward slashes)
- regex that contains spaces also be enclosed within " " (double quotation marks).

To negate regex, use the following syntax:

```
/{!regex}/
```

Be precise with your syntax so that it performs quickly and efficiently.

E.g. `/^NewYork-Router/` is faster than `/NewYork-Router/` because it specifies that the start of the match *must* begin with NewYork-Router.

For more information on regex, refer to *Regular Expressions Cookbook* (Goyvaerts & Levithan, 2012).

2.4 Time filters

AKIPS uses syntax for time filters in:

- reports and graphs
- threshold, alerting and availability rules.

AKIPS defines a week as 00:00:00 on Sunday to 23:59:59 on Saturday.

Syntax	Description	Example
<code>m</code>	minute	<code>7m</code>
<code>h</code>	hour	<code>2h</code>
<code>d</code>	day	<code>5d</code>
<code>w</code>	week	<code>6w</code>
<code>M</code>	month	<code>3M</code>
<code>y / yyyy</code>	year	<code>1y / 2021</code>
<code>yyyy q[1-4]</code>	year and quarter	<code>2021 q2</code>
<code>yyyy-MM</code>	year and month	<code>2021-04</code>
<code>yyyy-MM-dd</code>	year, month and day	<code>2021-04-17</code>
<code>yyyy-MM-dd hh:mm</code>	year, month, day and time	<code>2021-04-17 15:30</code>

Use the following syntax:

```
{positive integer}{m h d w M y}
{ddd} {hh:mm} to {hh:mm}
{ddd} {hh:mm} to {ddd} {hh:mm}
{ddd} to {ddd} {hh:mm} to {hh:mm}
not {ddd} {hh:mm} to {hh:mm}
not {ddd} {hh:mm} to {ddd} {hh:mm}
not {ddd} to {ddd} {hh:mm} to {hh:mm}

thishour
lasthour
today
yesterday
thisweek
lastweek
thismonth
lastmonth
thisyear
lastyear
last{duration}
from yyyy to yyyy
from yyyy-mm to yyyy-mm
from yyyy-mm-dd to yyyy-mm-dd
from yyyy-mm-dd hh:mm to yyyy-mm-dd hh:mm
```

```
from yyyy for {duration}
from yyyy-mm for {duration}
from yyyy-mm-dd for {duration}
from yyyy-mm-dd hh:mm for {duration}
from {timestamp} to {timestamp}
from {point in time} to {point in time}
from {point in time} to {point in time} [+ duration]
from {point in time} [+ duration] to
{point in time} [+ duration]

now

startoflastminute
endoflastminute

startofthisminute
endofthisminute

startoflasthour
endoflasthour

startofthishour
endofthishour

startofyesterday
endofyesterday

startoftoday
endoftoday

startoflastweek
endoflastweek
```

`startofthisweek`

`endofthisweek`

`startoflastmonth`

`endoflastmonth`

`startofthismonth`

`endofthismonth`

`startoflastyear`

`endoflastyear`

`startofthisyear`

`endofthisyear`

2.4.1 `tf pairs` and `tf span`

The `tf pairs` command will display a series of start,end pairs which indicate valid time ranges within the time filter.

The human readable form of this is shown in the `tf dump` command.

E.g.

```
tf dump "lastweek; mon to fri 8:00 to 17:00"
```

```
tf pairs "lastweek; mon to fri 8:00 to 17:00"
```

The `tf span` command displays the total span of the time filter.

E.g.

```
tf dump "lastweek; mon to fri 8:00 to 17:00"
```

```
tf span "lastweek; mon to fri 8:00 to 17:00"
```

Examples

The past 30 minutes:

```
tf dump last30m
```

```
span 2021-03-06 09:20:50 to 2021-03-06 09:50:50
```

The past 24 hours:

```
tf dump last24h
```

```
span 2021-03-05 10:05:56 to 2021-03-06 10:05:56
```

The previous day (until midnight this morning):

```
tf dump last1d
```

```
span 2021-03-06 00:00:00 to 2021-03-06 23:59:59
```

The previous seven days (until midnight this morning):

```
tf dump last7d
```

```
span 2021-02-28 00:00:00 to 2021-03-06 23:59:59
```

During business hours for the past week:

```
tf dump "lastweek; mon to fri 8:00 to 17:00"
```

```
span 2021-02-24 00:00:00 to 2021-03-02 23:59:59
include 2021-02-25 08:00:00 to 2021-02-25 17:00:00
include 2021-02-26 08:00:00 to 2021-02-26 17:00:00
include 2021-02-27 08:00:00 to 2021-02-27 17:00:00
include 2021-02-28 08:00:00 to 2021-02-28 17:00:00
include 2021-03-01 08:00:00 to 2021-03-01 17:00:00
```

During trading hours (with Thursday-evening trading) for the past week:

```
tf dump "lastweek; mon to fri 8:00 to 17:00; thu 8:00 to 21:00"
```

```
span 2021-02-24 00:00:00 to 2021-03-02 23:59:59
include 2021-02-25 08:00:00 to 2021-02-25 17:00:00
include 2021-02-26 08:00:00 to 2021-02-26 17:00:00
include 2021-02-27 08:00:00 to 2021-02-27 17:00:00
include 2021-02-28 08:00:00 to 2021-02-28 21:00:00
include 2021-03-01 08:00:00 to 2021-03-01 17:00:00
```

Outside trading hours (with Saturday-morning trading) for the past week:

```
tf dump "lastweek; not mon to fri 8:00 to 17:00; not sat 8:00 to 12:00"
```

```
span 2021-02-24 00:00:00 to 2021-03-02 23:59:59
include 2021-02-24 00:00:00 to 2021-02-25 08:00:00
include 2021-02-25 17:00:00 to 2021-02-26 08:00:00
include 2021-02-26 17:00:00 to 2021-02-27 08:00:00
include 2021-02-27 17:00:00 to 2021-02-28 08:00:00
include 2021-02-28 17:00:00 to 2021-03-01 08:00:00
include 2021-03-01 17:00:00 to 2021-03-02 08:00:00
include 2021-03-02 12:00:00 to 2021-03-02 23:59:59
```

During business hours in the first quarter of 2021:

```
tf dump "2021 q1; mon to fri 8:00 to 17:00"

span 2021-01-01 00:00:00 to 2021-03-31 23:59:59
include 2021-01-01 08:00:00 to 2021-01-01 17:00:00
include 2021-01-02 08:00:00 to 2021-01-02 17:00:00
include 2021-01-03 08:00:00 to 2021-01-03 17:00:00
...
include 2021-03-28 08:00:00 to 2021-03-28 17:00:00
include 2021-03-29 08:00:00 to 2021-03-29 17:00:00
```

The past 30 minutes:

```
tf dump "from now - 1h to now - 30m"

span 2021-03-06 09:30:58 to 2021-03-06 10:00:58
```

Today until now:

```
tf dump "from startoftoday to now"

span 2021-03-06 00:00:00 to 2021-03-06 10:33:13
```

Business hours on 1 February 2021:

```
tf dump "2021-02-01 8:00 to 17:00"

span 2021-02-01 08:00:00 to 2021-02-01 17:00:00
```

After business hours on 1 February 2021:

```
tf dump "from 2021-02-01 18:00 to 2021-02-02 06:00"

span 2021-02-01 18:00:00 to 2021-02-02 06:00:00
```

The first two months of 2021:

```
tf dump "from 2021 for 2M"

span 2021-01-01 00:00:00 to 2021-03-01 00:00:00
```

Yesterday from midday for three hours:

```
tf dump "from startofyesterday + 12h to startofyesterday + 15h"  
  
span 2021-03-05 12:00:00 to 2021-03-05 15:00:00
```

2.4.2 tf check

The `tf check` command will display either `1` (true) or `0` (false) depending on whether the given point in time (Unix epoch time) is within the time filter.

Use the following syntax:

```
tf check {point in time} "{time filter}"
```

Examples

```
tf check 1594771234 "from 2020-07-05 to 2020-07-11"
```

```
0
```

```
ok: tf check 1594771234 "from 2020-07-05 to 2020-07-11"
```

```
tf check 1594771234 "from 2020-07-12 to 2020-07-18"
```

```
1
```

```
ok: tf check 1594771234 "from 2020-07-12 to 2020-07-18"
```

2.5 IP address filters

You can use IP address filters throughout AKIPS.

Use the following syntax:

```
{address}/{mask}
```

```
{address}.*
```

```
{address} [{range}]
```

```
{address} [{range}] / {mask}
```

```
{address} [{range}] .*
```

Examples

A single IPv4 address:

```
10.1.1.50
```

```
10.1.1.50
```

All addresses in a single logical network (i.e. with a specified 24-bit prefix):

```
10.0.0.0/24
```

```
10.0.0.*
```

```
10.0.0.0
```

```
10.0.0.1
```

```
...
```

```
10.0.0.254
```

```
10.0.0.255
```

A host ID in a range of 256 logical networks (within a specified range of 256 concurrent 24-bit blocks):

10.0.0-255.1

10.0.*.1

10.0.0.1

10.0.1.1

10.0.2.1

...

10.0.255.1

A single IPv6 address:

fd00:10:1:1::1

fd00:10:1:1::1

Two hundred and fifty-six IPv6 addresses in a single logical network:

fd00:10:1:1::0-ff

fd00:10:1:1::0

fd00:10:1:1::1

...

fd00:10:1:1::fe

fd00:10:1:1::ff

A host ID in a range of 50 logical networks:

fd00:10:1:1-50:1

fd00:10:1:1::1

fd00:10:1:2::1

...

fd00:10:1:50::1

Chapter 3

Database overview

3.1 Entities

The ADB architecture defines three levels of entities:

- parents (see 3.1.1)
- childs (see 3.1.2)
- attributes (see 3.1.3).

You must create entities in the following order:

- create the **parent** before you add a **child**
- create the **child** before you add an **attribute**.

Each entity must have a type, which you cannot change once created.

Level	Entity	Type	Value	Notes
1	parent	Y	N	a parent is an independent item
2	child	Y	optional	a child is a component of its parent entity
3	attribute	Y	Y	an attribute is a component of its parent and child entities

Example

To measure the flow of traffic (by counting the number of incoming bytes, or InOctets) for a particular router:

- the parent is a device
- the child is an interface
- the attribute is a counter.

You could define it as:

Level	Entity	Type	Value	Name
1	parent	device router01		
2	child	interface	1,Test network	Se1/1
3	attribute	counter	1	IF-MIB.ifHC InOctets

3.1.1 Level 1: parent

Parent types:

- parent (generic)
- device
- user
- report.

3.1.2 Level 2: child

Child types:

- child (generic)
- interface
- ipsla
- memory
- processor
- storage
- system
- temperature.

A child may optionally have a value in the format of index,[description]

E.g. a child, Fa0/1, may be assigned a value of 1,Link to server:

- **1** is the ifIndex of the interface in ifTable
- **Link to server** is the ifAlias.

3.1.3 Level 3: attribute

Attribute types:

Type	Value	Example
counter	must be 1	1
enum	positive integer,text (enumerated list)	1,up 2,down
gauge	scale: integer (positive to multiply, negative to divide)	-2
integer	positive or negative whole number or 0	100287
RTT	positive integer (microseconds)	430
text	up to 2000 characters	the quick brown fox
timestamp	seconds since start of Unix epoch	1406787487
uptime	seconds since status change	13095

3.1.4 Virtual attributes

AKIPS doesn't poll virtual attributes but instead meaningfully interprets the data. E.g. ifutil is the in-rate divided by the interface speed.

Virtual attribute types:

Type	Description
ifutil	interface utilisation
ifrate	interface bps
vutil	utilisation
vnutil	calculate used from free
vdiff	difference $x = a - b$
temp_f	convert C to F

3.2 Groups

When you create a group, specify the group type. You can assign an entity only to a group with the same type.

A child inherits group assignments from its parent.

An attribute inherits group assignments from both its child and parent.

3.2.1 Super groups

Use super groups (groups of groups) to create a hierarchy of your network.

You cannot assign an entity directly to a super group. You can assign only a group to a super group.


Example

Assign a **router** on **floor 1** of **building A** to both:

- **floor 1** group
- **building A router** group.

Further assign the **building A router** group to both:

- **building A** super group
- **router** super group.



Graphic 1: mapping a hierarchy of groups and super groups

To edit a super group:

Go to **Admin > Grouping > Manual Grouping**.

Click **Super Groups**.

Select the relevant super group.

To change the super group's name:

Overtyping the name.

Click **Rename**.

To edit the super group's configuration:

Click **Edit**.

Select or deselect the relevant checkboxes

To delete the super group:

Click **Delete**.

The screenshot displays the AKiPS web interface. At the top, there is a navigation bar with the AKiPS logo and menu items: Dashboards, Reports, Tools, Admin, New, and PDF. On the right side of the navigation bar, it shows 'Licensed to demo1 v21.7.1' and 'User: admin'. Below the navigation bar, the main content area is titled 'Manual Grouping'. On the left, there is a vertical list of categories: CPUs, Devices, IPSLA, Interfaces, Memory, Netflow Exporters, Storage, Super Groups, and Temperature. Below this list are three buttons: 'Help', 'Grouping Rules', and 'Delete Broken Rules'. In the center, there is a 'Super Groups' section with an input field and an 'Add' button. Below the input field, a list of super groups is shown: '0-Airport' (highlighted in blue), '7-EMEA', and 'Region-A'. On the right, there is a 'Save' button and the title '0-Airport'. Below this, there is a list of items with checkboxes: '0-AU-VIC-BAL', '0-AU-VIC-GEE', '0-AU-VIC-MEL', '0-Building-3', '0-Building-4', '0-Melbourne', '0-MyGov', '0-Sydney' (checked), '0-Test', '1-Building-3', '1-Building-4', '1-Building-16', '1-Fraser', '1-Network-A', '1-Network-B', and '1-Notre-Dame-Test'.

Graphic 2: editing a super group's configuration

3.2.2 Configuring groups

Use the web API to manually:

- add or delete a group or super group
- assign an entity to a group
- assign a group to a super group
- remove an entity from a group
- remove a group from a super group.

Examples

CPU

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=processor;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=processor;group={group_name};  
mode=assign;device={device_name};child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=processor;group={group_name};  
mode=clear;device={device_name};child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=processor;group={group_name};  
mode=delete"
```

Device

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=device;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=device;group={group_name};  
mode=assign;device={device_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=device;group={group_name};  
mode=clear;device={device_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=device;group={group_name};  
mode=delete"
```

IPSLA

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=ipsla;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=ipsla;group={group_name};  
mode=assign;device={device_name};child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=ipsla;group={group_name};  
mode=clear;device={device_name};child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=ipsla;group={group_name};  
mode=delete"
```

Interface

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=interface;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=interface;group={group_name};  
mode=assign;device={device_name};child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=interface;group={group_name};  
mode=clear;device={device_name};child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=interface;group={group_name};  
mode=delete"
```

Memory

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=memory;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=memory;group={group_name};  
mode=assign;device={device_name};child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=memory;group={group_name};  
mode=clear;device={device_name};child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=memory;group={group_name};  
mode=delete"
```

NetFlow

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=flow;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=flow;group={group_name};  
mode=assign;device={device_name};child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=flow;group={group_name};  
mode=clear;device={device_name};child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=flow;group={group_name};  
mode=delete"
```

Storage

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=storage;group={group_name};  
mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=storage;group={group_name};  
mode=assign;device={device_name};child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=storage;group={group_name};  
mode=clear;device={device_name};child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=storage;group={group_name};  
mode=delete"
```

Super group

Add a super group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=super;  
group={super_group_name};mode=add"
```

Assign a group to a super group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=group;group={group_name};  
mode=assign;device={group_name}"
```

Remove a group from a super group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=group;group={group_name};  
mode=clear;device={group_name}"
```

Delete a super group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=super;  
group={super_group_name};mode=delete"
```

Temperature

Add a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=temperature;  
group={group_name};mode=add"
```

Assign an entity to a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=temperature;  
group={group_name};mode=assign;device={device_name};  
child={child_name}"
```

Remove an entity from a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=temperature;  
group={group_name};mode=clear;device={device_name};  
child={child_name}"
```

Delete a group:

```
curl -s "http://{server}/api-script?password={pwd};  
function=web_manual_grouping;type=temperature;  
group={group_name};mode=delete"
```

3.3 Events records

AKIPS stores events records in chronologically ordered blocks.

After 72 hours, AKIPS compresses and archives events records. You will not be able to edit or delete these.

Events records may include:

- enumeration changes
- uptime resets
- threshold events.

Each record in the events database includes:

- event time (epoch timestamp)
- entity (parent, child or attribute)
- flags (critical, enum, threshold and uptime)
- value.

To view enumeration and uptime attributes:

Go to **Admin > Alerting > Status Alerts**.

Scroll down the right-hand side of the page to find the table of **Status Attributes**.

To view threshold attributes:

Go to **Admin > Alerting > Threshold Alerts**.

Scroll down the right-hand side of the page to find the table of **Threshold Attributes**.

3.4 Time series

The features for time series include:

- three years of historical data
- 60-second values (no rollups or averages of stored data)
- 30-day blocks.

Rolling averages are available for the past five minutes to 30 days.

Time-series data types are:

- counters
- gauges
- RTT (microseconds).

Chapter 4

Config and events

4.1 Entity commands

4.1.1 add

Use the `add` command to create a new entity.

If the entity already exists, AKIPS will update it.

You cannot change an entity's type once created.

Use the following syntax:

```
add {type} {parent name}
```

```
add {type} {parent name} {child name} = [{index],[description}]
```

```
add {type} {parent name} {child name} {attribute name}  
[= {value}]
```

Examples

Add a router with an interface:

```
add device Router1

add system Router1 sys = 0

add text Router1 sys SNMPv2-MIB.sysName = "Router1.akips.com"

add text Router1 sys SNMPv2-MIB.sysLocation = "Test Rack"

add text Router1 sys SNMPv2-MIB.sysDesc = "Cisco IOS 7200
Version 12.4(9) T RELEASE (fc1)"

add text Router1 sys SNMPv2-MIB.sysContact = "AKIPS developers"

add uptime Router1 sys SNMPv2-MIB.sysUpTime = 1432703430

add text Router1 sys ip4addr = 10.1.8.250

add text Router1 sys ip6addr = fd00:10:1:8::250

add system Router1 ping4 = "4,10.1.8.4"

add rtt Router1 ping4 PING.icmpRtt

add counter Router1 ping4 PING.icmpDup

add counter Router1 ping4 PING.icmpLost

add enum Router1 ping4 PING.icmpState = 2,up

add system Router1 ping6 = "6,fd00:10:1:8::250"

add rtt Router1 ping6 PING.icmpRtt

add counter Router1 ping6 PING.icmpDup

add counter Router1 ping6 PING.icmpLost

add enum Router1 ping6 PING.icmpState

add interface Router1 Fa0/0 = "1,Link to remote site"

add integer Router1 Fa0/0 IF-MIB.ifSpeed = 1000000000
```

```
add text Router1 Fa0/0 IF-MIB.ifAlias = "Link to remote site"

add counter Router1 Fa0/0 IF-MIB.ifHCInOctets = 1

add counter Router1 Fa0/0 IF-MIB.ifHCOutOctets = 1

add enum Router1 Fa0/0 IF-MIB.ifAdminStatus = 1,up

add enum Router1 Fa0/0 IF-MIB.ifOperStatus = 1,up

add counter Router1 Fa0/0 IF-MIB.ifHCInBroadcastPkts = 1

add counter Router1 Fa0/0 IF-MIB.ifHCOutBroadcast Pkts = 1

add counter Router1 Fa0/0 IF-MIB.ifHCInMulticastPkts = 1

add counter Router1 Fa0/0 IF-MIB.ifHCOutMulticast Pkts = 1
```

Add some custom entries for asset information:

```
add child Router1 asset

add text Router1 asset serial_number = 123456789

add text Router1 asset purchase_date = 2017/05/02

add integer Router1 asset purchase_cost = 12013
```

4.1.2 delete

Use the `delete` command to remove a single entity, including all of its childs and attributes.

Use the following syntax:

```
delete {type} {parent name} [[{child name}] {attribute name}]
```

Examples

Delete a device:

```
delete device CoreRouter12
```

Delete a child:

```
delete interface CoreRouter1 Fa0/03
```

Delete an attribute:

```
delete integer CoreRouter1 Fa0/0 IF-MIB.ifSpeed
```

4.1.3 get

Use the `get` command to return the value assigned to a child or attribute.

Use the following syntax:

```
get {parent name} {child name} [{attribute name}]
```

Examples

Get the value for an interface:

```
get swt250 Fa0/1
```

```
10001,Link to swt2512
```

Get the value for an attribute:

```
get swt250 sys SNMPv2-MIB.sysLocation
```

```
Test room
```

The `get` command for an attribute with a type of uptime returns two values separated by a comma:

1. when the value was reset to zero (epoch timestamp)
2. when the attribute value was last updated (epoch timestamp).

Example

```
get swt250 sys SNMPv2-MIB.sysUpTime
```

```
1427283250,1433815768
```

The `get` command for an attribute with a type of enum returns five values separated by commas:

1. list number (from MIB)
2. text value (from MIB)
3. time created (epoch timestamp)
4. time modified (epoch timestamp)
5. child description.

Example

```
get swt250 Fa0/1 IF-MIB.ifOperStatus
```

```
1,up,1431579447,1431579447,link to swt251
```

4.1.4 mdelete

Use the `mdelete` command to remove several entities at once. You can test your selection first with `mget` (see 4.1.5).

You can use `regex` to precisely target the entities.

Use the following syntax:

```
mdelete {type} {parent regex} [{child regex}
[attribute regex]]
```

Examples

Delete all devices (We do not recommend this!):

```
mdelete device *
```

Delete all devices in a group:

```
mdelete device * any group testlab
```

Delete all IF-MIB attributes:

```
mdelete * CoreRouter1 Fa0/0 /IF-MIB/
```

Delete all ipsla entities for a device:

```
mdelete * Corerouter1 /ipsla/
```

4.1.5 mget

Use the `mget` command to retrieve large amounts of configuration information.

Use the following syntax:

```
mget {type}
```

Examples

```
mget device
```

```
mget user
```

```
mget interface
```

```
mget processor
```

```
mget system
```

You can also add regex.

Use the following syntax:

```
[{parent regex} [{child regex} [{attribute regex}]]]  
[value {text|/regex|integer|ipaddr}] [profile {profile name}]  
[any|all|not group {group name} ...
```

The format of the return values depends on which entity (parent, child or attribute) you request.

If you request a parent then the type must be a parent or a wildcard, e.g.

```
mget * /~nyc-.*-rtr/
```

```
mget device *
```

```
mget user *
```

If you request a child then the type must be a child or a wildcard, e.g.

```
mget * swt250 /~Fa/
```

```
mget system swt250 *
```

```
mget interface * *
```

```
mget interface * /~Fa0/1/
```

If you request an attribute then the type must be an attribute or a wildcard, e.g.

```
mget * swt250 * *
```

```
mget counter swt250 Fa0/1 /IF-MIB/
```

Examples

Retrieve the entire configuration for a single device:

```
mget * swt250 * *
```

Retrieve the sysName for each device:

```
mget text * * SNMPv2-MIB.sysName
```

```
Atlanta-ro sys SNMPv2-MIB.sysName = Atlanta-ro.akips.com  
Baltimore-ro sys SNMPv2-MIB.sysName = Baltimore-ro.akips.com  
Boston-ro sys SNMPv2-MIB.sysName = Boston-ro.akips.com  
Charlotte-ro sys SNMPv2-MIB.sysName = Charlotte-ro.akips.com  
cisco-74-1-1 sys SNMPv2-MIB.sysName = cisco-74-1-1
```

Retrieve all IF-MIB objects for a single interface:

```
mget * swt250 Fa0/1 /^IF-MIB.*/

swt250 Fa0/1 IF-MIB.ifAdminStatus = 1,up,1434416774,1434416774
swt250 Fa0/1 IF-MIB.ifAlias = Link to swt251
swt250 Fa0/1 IF-MIB.ifDescr = FastEthernet0/1
swt250 Fa0/1 IF-MIB.ifDuplex = 3,fullDuplex,1434416774,1434416774
swt250 Fa0/1 IF-MIB.ifHCInBroadcastPkts = 1
```

Retrieve the IPv4/6 addresses for each device:

```
mget text * sys /ip.addr/

Atlanta-ro sys ip4addr = 10.4.26.1
Atlanta-ro sys ip6addr = fd00:10:4:26::1
Baltimore-ro sys ip4addr = 10.4.22.1
Baltimore-ro sys ip6addr = fd00:10:4:22::1
Boston-ro sys ip4addr = 10.4.23.1
Boston-ro sys ip6addr = fd00:10:4:23::1
...
```

Case study

A customer used the `mget` command to obtain the serial numbers of all devices on his network, including their access points:

```
mget * * * /serial/
```

4.1.6 mlist

Use the `mlist` command to retrieve a list of matching entities.

Unlike the `mget` command, the output does not contain any entity values.

Use the following syntax:

```
mlist {type} [{parent regex} [{child regex} [{attribute regex}]]]
[value {text|/regex/|integer|ipaddr}] [profile {profile name}]
[any|all|not group {group name} ...
```

Examples

Retrieve a list of all interfaces on a device:

```
mlist interface swt250 *
```

```
swt250 Fa0/1
swt250 Fa0/10
swt250 Fa0/11
swt250 Fa0/12
swt250 Fa0/16
...
```

Retrieve a list of interface attributes on a device with the type counter:

```
mlist counter
```

```
swt250 * /^IF-MIB./
swt250 Fa0/1 IF-MIB.ifHCInBroadcastPkts
swt250 Fa0/1 IF-MIB.ifHCInMulticastPkts
swt250 Fa0/1 IF-MIB.ifHCInOctets
swt250 Fa0/1 IF-MIB.ifHCInUcastPkts
swt250 Fa0/1 IF-MIB.ifHCOutBroadcastPkts
swt250 Fa0/1 IF-MIB.ifHCOutMulticastPkts
swt250 Fa0/1 IF-MIB.ifHCOutOctets
swt250 Fa0/1 IF-MIB.ifHCOutUcastPkts
swt250 Fa0/1 IF-MIB.ifInDiscards
swt250 Fa0/1 IF-MIB.ifInErrors
...
```

Retrieve a list of enumerated attribute types configured for a device:

```
mlist enum swt250 * *  
  
swt250 cstack.1 CISCO-STACK-MIB.moduleStandbyStatus  
swt250 cstack.1 CISCO-STACK-MIB.moduleStatus  
swt250 Fa0/1 IF-MIB.ifAdminStatus  
swt250 Fa0/1 IF-MIB.ifDuplex  
swt250 Fa0/1 IF-MIB.ifOperStatus  
swt250 Fa0/1 IF-MIB.ifType  
swt250 Fa0/10 IF-MIB.ifAdminStatus  
...
```

4.1.7 mtype

Use the `mtype` command to retrieve a list of matching entities.

Unlike the `mget` command, the output contains entity types, not values.

Use the following syntax:

```
mtype {type} [{parent regex} [{child regex} [{attribute regex}]]]
[value {text|/regex|integer|ipaddr}] [profile {profile name}]
[any|all|not group {group name} ...]
```

Examples

Retrieve a list of childs for a device:

```
mtype * swt250 *

swt250 cpu.1 processor
swt250 cstack.1 child
swt250 Fa0/1 interface
...
swt250 Gi0/1 interface
swt250 Gi0/2 interface
swt250 ipsla.1 ipsla
swt250 ipsla.2 ipsla
swt250 ping6 system
swt250 psu.1003 system
swt250 ram.1 memory
swt250 ram.2 memory
swt250 sys system
```

Retrieve a list of attributes for a device:

```
mtype * swt250 * *  
  
swt250 cpu.1 CISCO-PROCESS-MIB.cpmCPUTotal1minRev gauge  
swt250 cstack.1 CISCO-STACK-MIB.moduleModel text  
swt250 cstack.1 CISCO-STACK-MIB.moduleStandbyStatus enum  
swt250 cstack.1 CISCO-STACK-MIB.moduleStatus enum  
swt250 Fa0/1 IF-MIB.ifAdminStatus enum  
swt250 Fa0/1 IF-MIB.ifAlias text  
swt250 Fa0/1 IF-MIB.ifDescr text  
swt250 Fa0/1 IF-MIB.ifDuplex enum  
swt250 Fa0/1 IF-MIB.ifHCInBroadcastPkts counter  
swt250 Fa0/1 IF-MIB.ifHCInMulticastPkts counter  
...
```

4.1.8 rename

Use the `rename` command to rename a parent or child.

Use the following syntax:

```
rename {type} {existing parent name} {new parent name}  
  
rename {type} {existing parent name} {existing child name}  
{new parent name} {new child name}
```

Examples

Rename a device:

```
rename device nyc-rtr usa-nyc-rtr12
```

Move an interface from one device to another:

```
rename interface nyc-rtr1 Se0/1 nyc-rtr2 Se0/1
```

4.1.9 set

Use the `set` command to update an entity's value.

Use the following syntax:

```
set {parent name} {child name} [{attribute name}] = {value}
```

Examples

```
set swt250 sys SNMPv2-MIB.sysLocation = "AKIPS Test Lab"
```

```
set swt250 sys SNMPv2-MIB.sysContact = "AKIPS developers"
```

```
set swt250 sys ip4addr = 10.1.8.250
```

4.2 Group commands

4.2.1 add

Use the `add` command to create a new group.

If the group already exists, AKIPS will not update it.

You cannot change a group's type once created.

Use the following syntax:

```
add {type} group {group name}
```

Examples

Add a group:

```
add device group core-routers
```

Add an interface group:

```
add interface group uplinks
```

Add an ipsla group:

```
add ipsla group Jitter-tests
```

Add device and super groups:

```
add device group SFO-BuildingA-F101
add device group SFO-BuildingA-F102
add device group SFO-BuildingA-F103
...
add device group SFO-BuildingB-F101
add device group SFO-BuildingB-F102
add device group SFO-BuildingB-F103
...
add super group SFO-BuildingA
add super group SFO-BuildingB
add super group SFO-Campus
```

Add interface and super groups:

```
add interface group SFO-BuildingA-switch-uplinks
...
add super group SFO-Campus-switch-uplinks
```

You can also use the `add` command to create a new profile group.

Use the following syntax:

```
add profile group {group name}
```

Example

```
add profile group WAN-Tech-Support
```

4.2.2 assign

Use the `assign` command to assign groups.

Use the following syntax:

```
assign group {group name} = {super group name}

assign {type} {parent regex} [{child regex} [{attribute regex}]]
[value {text|integer|/regex|ipaddr}] [profile {profile name}]
[any|all|not group {group name} ...] = {target group} ...
```

Examples

Create vendor groups and assign devices to them based on attribute values:

```
add device group Cisco

add device group Extreme

assign * * sys SNMPv2-MIB.sysDescr value /Cisco/ = Cisco

assign * * sys SNMPv2-MIB.sysDescr value /Cabletron/ = Extreme

assign * * sys SNMPv2-MIB.sysDescr value /Enterasys/ = Extreme

assign * * sys SNMPv2-MIB.sysDescr value /Extreme/ = Extreme
```

Put different models into groups using sysDescr:

```
add device group Cisco-3600

add device group Cisco-3700

add device group Cisco-7200

assign * * sys SNMPv2-MIB.sysDescr value "/Cisco IOS 3600/" =
Cisco-3600

assign * * sys SNMPv2-MIB.sysDescr value "/Cisco IOS 3700/" =
Cisco-3700

assign * * sys SNMPv2-MIB.sysDescr value "/Cisco IOS 7200/" =
Cisco-7200
```

Put different models into groups using sysObjectID:

```
add device group Cisco-3600

add device group Cisco-3700

add device group Cisco-7200

assign * * sys SNMPv2-MIB.sysObjectID value
/CISCO-PRODUCTS-MIB.cisco36/ = Cisco-3600

assign * * sys SNMPv2-MIB.sysObjectID value
/CISCO-PRODUCTS-MIB.catalyst37xxStack/ = Cisco-3700

assign * * sys SNMPv2-MIB.sysObjectID value
/CISCO-PRODUCTS-MIB.cisco72/ = Cisco-7200
```

Create some device groups:

```
add device group routers
add device group switches
add device group core-routers
add device group regional-routers
add device group core-switches
add device group regional-switches
```

Create some interface groups:

```
add interface group core-links
add interface group core-switch-uplinks
add interface group regional-links
add interface group servers
```

Assign interfaces to a group:

```
add interface group serial-links
assign interface * /~Se/ = serial-links27
```

Assign all links with a specific ifAlias to a group:

```
add interface group Switch-Uplinks
assign interface * * IF-MIB.ifAlias value /uplink/ =
Switch-Uplinks
```

Create a group hierarchy:

```
add device group central-office-fl01

assign device /central-office-fl01-.* / = central-office-fl01

add device group central-office-fl02

assign device /central-office-fl02-.* / = central-office-fl02

add super group central-office

assign group central-office-fl01 = central-office

assign group central-office-fl02 = central-office

add super group Brisbane

assign group central-office = Brisbane

add super group Queensland

assign group Brisbane = Queensland

add super group Australia

assign group Queensland = Australia
```

You can also use the `assign` command to assign a user or group to a profile group.

Use the following syntax:

```
assign user {user name} = {profile name}

assign {type} group {group regex} = {profile name}

assign group {group regex} = {profile name}
```

Examples

Allow a profile to access a device group:

```
assign device group Alcatel = Support
```

Allow a profile to access an interface group:

```
assign interface group ifspeed_10G = Support
```

Assign a user to a location profile:

```
assign user a.jager = Building02
```

Create a profile group and allow it to access specific devices:

```
add profile group WAN-Tech-Support
add device group WAN-Devices
assign * * sys SNMPv2-MIB.sysDescr value /Cisco/ = WAN-Devices
add report group WAN-Reports
assign * * config vendor value /Cisco/ = WAN-Reports
assign group WAN-Devices = WAN-Tech-Support
assign group WAN-Reports = WAN-Tech-Support
```

Create a profile group, assign a user and allow access to devices with a specific sysName:

```
add profile group Helpdesk-Profile
assign user fred = Helpdesk-Profile
add device group Helpdesk-Devices
assign * /-swt|-rtr/ = Helpdesk-Devices
assign group helpdesk-devices = Helpdesk-Profile
```

4.2.3 clear

Use the `clear` command to remove group assignments.

Use the following syntax:

```
clear group {group name} = {super group name} clear {type}
{parent regex} [{child regex} [{attribute regex}]]
[value {text|/regex/|integer|ipaddr}] [profile {profile name}]
[any|all|not group {group name} ...] = {target group} ...
```

Example

Assign devices to a group and then clear switches:

```
assign * * sys SNMPv2-MIB.sysDescr value /Cisco/ = Cisco

clear * * sys SNMPv2-MIB.sysDescr value "/Cisco IOS C3560/"
= Cisco
```

You can also use the `clear` command to remove entities from a profile group.

Use the following syntax:

```
clear user {user name} = {profile name}

clear group {group name} = {profile name}

clear group {group regex} = {profile name}

clear {type} group {group regex} = {profile name}
```

Examples

Remove a user from a profile group:

```
clear user a.jager = Cisco-Only
```

Remove a profile group's access to a device group:

```
clear group WAN-Device = WAN-Tech-Support
```

4.2.4 count

Use the `count` command to return the number of entities in a group.

Use the following syntax:

```
count {type} group {group regex}
```

Example

Count the number of interfaces in a group:

```
count interface group uplinks
```

4.2.5 delete

Use the `delete` command to remove a single group.

Use the following syntax:

```
delete {type} group {group name}
```

Examples

Delete a device group:

```
delete device group core-routers
```

Delete an interface group:

```
delete interface group uplinks
```

Delete a super group:

```
delete super group SFO-Campus
```

4.2.6 get

Use the `get` command to check if a group exists.

Use the following syntax:

```
get group {group name}
```

Example

```
get group Cisco
```

```
device
```

You can also use the `get` command to check if a profile group exists.

Use the following syntax:

```
get profile user {user name}
```

Example

Show the profile allocated to a user:

```
get profile user a.jager
```

```
Support
```

4.2.7 list

Use the `list` command to see the groups in a specific type.

Use the following syntax:

```
list {type} group [{parent name} [{child name}
  [{attribute name}]]] [profile {profile name}]
  [super {super group name}]
```

Examples

```
list profile group
```

```
list device group
```

```
list * group
```

You can also use the `list` command to find the profile groups associated with an entity.

Use the following syntax:

```
list profile {type} {parent name} [{child name}]
  {attribute name}]
```

Examples

Find the groups associated with a profile group:

```
list * group profile Support
```

```
super,Australia  
super,Brisbane  
super,central-office  
device,Cisco  
device,Dell  
interface,ifspeed_1  
interface,ifspeed_1.4G  
interface,ifspeed_1.5M  
interface,ifspeed_1.8
```

Find the devices associated with a profile group:

```
list device group profile Support
```

```
Cisco  
Dell
```

Find the interfaces associated with a profile group:

```
list interface group profile Support
```

```
ifspeed_1  
ifspeed_1.4G  
ifspeed_1.8G  
ifspeed_100G  
...
```

Find all of the super groups that a profile group can access:

```
list device super group profile Support
```

```
Australia  
Brisbane  
central-office
```

4.2.8 mget

Use the `mget` command to retrieve large amounts of configuration information for a profile group.

Use the following syntax:

```
mget {type} [{parent regex} [{child regex} [{attribute regex}]]]
[value {text|integer|/regex|ipaddr}] [profile {profile name}]
[any|all|not group {group name} ...]
```

Example

Show every device that a profile group can access:

```
mget device profile Cisco-Only
```

```
cisco-132-0-1
cisco-132-0-10
```

4.2.9 mlist

Use the `mlist` command to find entities associated with a profile group.

Use the following syntax:

```
mlist {type} [profile {profile name}]
```

Example

Show which devices a profile group can access:

```
mlist device profile fred
```

4.2.10 mtype

Use the `mtype` command to return an entity type for a profile group.

Use the following syntax:

```
mtype {type} [profile {profile name}]
```

Example

Show which entity types a profile group can access:

```
mtype * profile Fred
```

4.2.11 prune

Use the `prune` command to remove empty groups.

Use the following syntax:

```
prune {type} group [{group regex}]
```

Examples

Remove all empty device groups:

```
prune device group
```

Remove all empty interface groups:

```
prune interface group
```

4.2.12 rename

Use the `rename` command to rename a group. This will retain all of its associations.

Use the following syntax:

```
rename {type} group {existing group name} {new group name}
```

Examples

Rename a profile group:

```
rename profile group Support Network-Support
```

Rename a device group:

```
rename device group core-routers USA-Core-Routers
```

Rename an interface group:

```
rename interface group uplinks Switch-Uplinks
```

4.3 Event commands

Event flags include:

- **ack**
- **critical.** AKIPS automatically adds a critical event flag to entities which match `crit_event`
- **suppress**
- **warning.** AKIPS automatically adds a warning event flag to entities which match `warn_event`
- **above**
- **below.**

4.3.1 add

Use the `add` command to add an entity before creating an event.

You can use only the critical event flag with `add`.

Use the following syntax:

```
add event {time} {parent name} {child name} {attribute name}
[{{event flags}}] = {value}
```

Examples

Add `ifOperStatus` down and up events:

```
add event 0 swt250 Se0/1 IF-MIB.ifOperStatus = down
add event 0 swt250 Se0/1 IF-MIB.ifOperStatus = up
```

Add ping-down and SNMP-down events:

```
add event 0 swt250 ping4 PING.icmpState = down
add event 0 swt250 ping6 PING.icmpState = down
add event 0 swt250 sys snmp.snmpState = down
```

Create a site-specific admin state for a device which may be set by another system:

```
add enum swt250 sys admin_state
add event 0 swt250 sys admin_state = maintenance
add event 0 swt250 sys admin_state = online
```

4.3.2 clear

Use the `clear` command to clear a flag from an event.

Use the following syntax:

```
clear event {time} {parent name} {child name} {attribute name} =  
{event flags}
```

Example

Clear the critical flag on a ping-down event:

```
clear event 1435822220 swt250 ping4 ping.icmpState = critical
```

4.3.3 delete

Use the `delete` command to delete an event.

Use the following syntax:

```
delete event {time} {parent name} {child name} {attribute name}
```

Example

Delete a down event:

```
delete event 1435822225 swt250 ping4 PING.icmpState
```

4.3.4 mdelete

Use the `mdelete` command to delete all events for an attribute within a specific time range.

You can test your selection first with `mget` (see 4.3.5).

Use the following syntax:

```
mdelete event time {time filter} [{parent regex}
[{child regex} [{attribute regex}]]] [profile {profile name}]
[any|all|not group {group name} ...]
```

Example

Delete all IF-MIB.ifOperStatus events for devices in a group for yesterday:

```
mdelete event time yesterday * * IF-MIB.ifOperStatus any group
Edge-Switches
```

4.3.5 mget

Use the `mget` command to retrieve events records in chronological order.

The child description will display only if you include one in its configuration.

Use the following syntax:

```
mget event {all,critical,enum,threshold,uptime}
time {time filter} [{parent regex} {child regex}
{attribute regex}] [profile {profile name}]
[any|all|not group {group name} ...]
```

Enumerated events

Use the following syntax:

```
{epoch} {parent} {child} {attribute} enum {flags} {value}
[{child description}]
```

Uptime events

Use the following syntax:

```
{epoch} {parent} {child} {attribute} uptime {flags}
{last uptime in seconds} [{child description}]
```

Threshold events

Use the following syntax:

```
{epoch} {parent} {child} {attribute} threshold {flags}
{rule exceeded} [{child description}]
```

Examples

Retrieve all ping-outage events for a router for the past hour:

```
mget event enum time last1h Columbus-ro /ping/ *

1435894798 Columbus-ro ping4 PING.icmpState enum none down
10.4.1.22
1435894799 Columbus-ro ping6 PING.icmpState enum none down
fd00:10:4:1::22
1435895128 Columbus-ro ping4 PING.icmpState enum none up
10.4.1.22
1435895129 Columbus-ro ping6 PING.icmpState enum none up
fd00:10:4:1::22
```

Retrieve all ifOperStatus events for the past day:

```
mget event enum time last1d * * IF-MIB.ifOperStatus

1435846269 NewYork-ro Se2/2 IF-MIB.ifOperStatus enum none down
Link to San Francisco
1435846509 NewYork-ro Se2/2 IF-MIB.ifOperStatus enum none up
Link to San Francisco
1435848305 Chicago-ro Se1/4 IF-MIB.ifOperStatus enum none down
Link to Dallas
1435848365 Chicago-ro Se1/4 IF-MIB.ifOperStatus enum none up Link
to Dallas
```

Retrieve all sysUpTime resets:

```
mget event uptime time last1d

1435846486 Toronto-ro sys SNMPv2-MIB.sysUpTime uptime none 19044
1435848309 Columbus-ro sys SNMPv2-MIB.sysUpTime uptime none 7863
1435849250 Detroit-ro sys SNMPv2-MIB.sysUpTime uptime none 10363
1435849830 Cleveland-ro sys SNMPv2-MIB.sysUpTime uptime none
25704
```

Retrieve all threshold events for the past hour:

```
mget event threshold time last1h
```

```
1436104800 cisco-74-1-19 cpu.2 CISCO-PROCESS-MIB.cpm CPUTotal
1minRev threshold critical,above last5m,avg,60
1436104800 Chicago-ro ping4 PING.icmpRtt threshold critical,below
last30m,avg,40000
1436104800 cisco-74-1-38 cpu.26 CISCO-PROCESS-MIB.cpm CPUTotal
1minRev threshold critical,above last5m,avg,60
1436105101 SanFrancisco-ro ping4 PING.icmpRtt threshold
critical,above last30m,avg,40000
1436105101 cisco-74-1-17 cpu.4 CISCO-PROCESS-MIB.cpm CPUTotal
1minRev threshold critical,below last5m,avg,60
1436105101 cisco-74-1-29 cpu.2 CISCO-PROCESS-MIB.cpm CPUTotal1min
threshold critical,above last5m,avg,60
1436105101 cisco-74-1-30 cpu.2 CISCO-PROCESS-MIB.cpm CPUTotal1min
threshold critical,above last5m,avg,60
1436105101 NewYork-ro ping6 PING.icmpRtt threshold critical,above
last30m,avg,40000
1436105101 NewYork-ro ping4 PING.icmpRtt threshold critical,above
last30m,avg,40000
1436105101 Chicago-ro ping4 PING.icmpRtt threshold critical,above
last30m,avg,40000
```

4.3.6 set

Use the `set` command to set event flags.

Use the following syntax:

```
set event {time} {parent name} {child name} {attribute name} =
{event flags}
```

Example

Set a critical flag on an existing ping-down event:

```
set event 1435822220 swt250 ping4 ping.icmpState = critical
```

4.3.7 tget

Use the `tget` command to return time-series values for a number of events per interval.

Use the following syntax:

```
tget event {all,critical,enum,threshold,uptime} {interval secs}
time {time filter} [{parent regex} [{child regex}
[{attribute regex}]]] [profile {profile name}]
[any|all|not group {group name} ...]
```

Example

Retrieve time-series values for all ping events for yesterday in 24 one-hour intervals:

```
tget event all 3600 time yesterday * /ping/
```

```
506,426,460,458,440,760,315,301,232,421,332,288,196,299,380,381,
495,448,497,570,386,430,362,530
```

4.4 Time-series commands

4.4.1 calc

Use the `calc` command to calculate a total, average or median value.

Use the following syntax:

```
calc total|avg|{median NN} time {time filter}
{type} {parent name} {child name} {attribute regex}
[profile {profile name}] [any|all|not group {group name} ...]
```

Examples

Calculate the total InOctets for a switch interface for yesterday:

```
calc total time yesterday counter swt250 Fa0/1 /InOctets/
```

Calculate the average InOctets for a switch interface for yesterday:

```
calc avg time yesterday counter swt250 Fa0/1 /InOctets/
```

4.4.2 mcalc

Use the `mcalc` command to calculate multiple total, average or median values.

Use the following syntax:

```
mcalc total|avg|{median NN} time {time filter}
{type} {parent regex} {child regex} {attribute regex}
[profile {profile name}] [any|all|not group {group name} ...]
```

Example

Calculate the In/OutOctets for all interfaces in a group:

```
mcalc total time yesterday counter * * /^IF-MIB.*InOctets|
^IF-MIB.*OutOctets/ any group wan-links mcalc avg time last1m
ifutil swt5 Gi2/0/1 *
```

```
Chicago-ro Se1/0 IF-MIB.ifInOctets = 90922240
Chicago-ro Se1/0 IF-MIB.ifOutOctets = 112385280
Chicago-ro Se1/1 IF-MIB.ifInOctets = 0
Chicago-ro Se1/1 IF-MIB.ifOutOctets = 0
Chicago-ro Se1/2 IF-MIB.ifInOctets = 11374963
Chicago-ro Se1/2 IF-MIB.ifOutOctets = 10454049
Chicago-ro Se1/3 IF-MIB.ifInOctets = 11409152
```

Case study

A customer used the `mcalc` command to export the utilisation data (bits in or out) from groups of interfaces for specific device groups, for the previous five minutes as an average:

```
mcalc avg time last5m ifrate * * /IF-MIB.if.*BitRate/
any group Circuit
```

4.4.3 mget

Use the `mget` command to test if an average has crossed a defined threshold.

For threshold examples, see **Admin > Alerting > Threshold Alerts**.

Use the following syntax:

```
mget last{duration} total|avg|nonzero
[above|below {value}[%]] [time {time filter}]
{type} {parent regex} {child regex} {attribute regex}
[profile {profile name}] [any|all|not group {group name} ...]
```

Examples

Retrieve a list of devices in a group whose average ping RTTs have exceeded a specific value in a specific timeframe:

```
mget last1h avg above 10000 rtt * /ping/ * any group data-center2
```

Retrieve a list of interfaces in a group whose usage have exceeded a specific percentage in a specific timeframe:

```
mget last5m avg above 80% * * * /ifInUtil|ifOutUtil/
any group wan-links3
```

Retrieve a list of devices whose CPU usage have exceeded a specific percentage in a specific timeframe:

```
mget last5m avg above 60 * * * /CISCO-PROCESS-MIB.cpmCPU
Totalmin/
```

4.4.4 series

Use the `series` command to return time-series values for a selected time range.

Use the following syntax:

```
series [interval total|avg {secs}] time {time filter}
{type} {parent regex} {child regex} {attribute regex}
[profile {profile name}] [any|all|not group {group name} ...]
```

Example

Retrieve the total In/OutOctet values for an interface:

```
series interval total 3600 time yesterday counter swt250
Fa0/1/InOctets|OutOctets/

swt250 Fa0/1 IF-MIB.ifHCInOctets = 2524672,2463360,2449920,
2447488,2486656,2488064,2457856,...
swt250 Fa0/1 IF-MIB.ifHCOutOctets = 975552,806976,803392,
822016,802496,894144,820480,820608,...
```

4.4.5 top

Use the `top` command to retrieve information on the highest number of events of a particular type within a selected time range.

Use the following syntax:

```
top {N} [reverse] [interval avg {secs}]
total|max|avg|median {NN} time {time filter}
{type} {parent regex} {child regex} {attribute regex}
[profile {profile name}] [any|all|not group {group name} ...]
```

Example

Retrieve the interfaces with the highest In/OutOctets for yesterday:

```
top 20 total time yesterday counter * * /IF-MIB.if.*Octets/

cisco-74-1-12 Te1/1 IF-MIB.ifHCInOctets = 134374989234176
cisco-74-1-16 Te1/1/1 IF-MIB.ifHCOutOctets = 92564298924032
juniper-74-2-7 xe-0/0/10.0 IF-MIB.ifHCInOctets = 92329710977024
juniper-74-2-12 ae47.0 IF-MIB.ifHCOutOctets = 92308460535808
cisco-74-1-24 Ethernet1/23 IF-MIB.ifHCOutOctets = 89412016799744
cisco-74-1-24 Ethernet1/24 IF-MIB.ifHCOutOctets = 88919019356160
juniper-74-2-10 reth0.2213 IF-MIB.ifHCOutOctets = 88832066191360
arista-74-0-40 Ethernet5/6 IF-MIB.ifHCInOctets = 88685106167808
cisco-74-1-17 Po55.152 IF-MIB.ifHCOutOctets = 88431959736320
...
```

4.5 Web API

Instead of using the command console (see 2.2) or SSH, you can transport commands via HTTP.

Use the following syntax:

```
http://{server}/api-db?password={pw};cmds={query}
```

The `api-rw` user can run any API command.

The `api-ro` user can use any of the following commands:

`aggregate`

`calc`

`check`

`count`

`cseries`

`get` (url encode the query, e.g. replace each space with +)

`list`

`mcalc`

`mget`

`mgroup`

`mlist`

`mtime`

`mtype`

`netmask`

`rget`

series

tf

tget

top

tz

To activate the config and events web API:

Go to **Admin > API > Web API Settings**.

Click the **Config and Events** option **On**.

Click **Save**.

The screenshot shows the AKIPS Web API Settings page. The 'Config and Events' option is highlighted with a red box and is set to 'On'. The page includes sections for 'Availability', 'Config and Events', and 'Config and Events' (repeated). The 'Config and Events' section contains a table of options and a permissions table.

Web API Settings

Availability off
Default: off

Config and Events On
Default: off

Config Viewer On
Default: off

HTTP Log off
Default: off

NetFlow off
Default: off

NetFlow Time-series off
Default: off

Site Script Functions On
Default: off

Switch Port Mapper On
Default: off

Syslog and Traps On
Default: off

Unused Interfaces On
Default: off

Save

Availability

This is a Web API wrapper around the nm-availability program.
Refer to the AKIPS programming guide.

Access:
Requires a username of `api-ro`

Syntax:
`http://{server}/api-availability?password=(pw);(option)=(value);...`

Options:

Option	Value	Comment
maintenance	on off	Show/hide maintenance mode devices
mode	group device events	One only
time	(time filter)	Refer to the programming guide
report	ping4, ping6, snmp, ifstatus	Any combination, comma separated
entity	{device} {childid}	
group	{group_name}	
profile	{profile_name}	

Example:
`http://{server}/api-availability?password=(pw).mode=group;time=lastId;report=ping4`

Sample Output:

```
ping4,PING,icmpState,Cisco,817150,815400,10000,lastId
ping4,PING,icmpState,FreeBSD,5832,5832,9500,lastId
```

Config and Events

This is a Web API wrapper around the nm-db program.
Refer to the *API Programming Guide*.

Access:
Requires a username of `api-ro` and/or `api-rw`.

Username	Permissions
api-ro	Read-only commands
api-rw	All commands

Graphic 3: activating the config and events web API

Go to **Admin > Users / Profiles > User Settings**.

In the **Username** text field, type `api-rw`

Complete the remaining text fields.

Click **Add**.

The screenshot shows the 'User Settings' page in the AKiPS interface. The 'Username' field is highlighted with a red box and contains the text 'api-rw'. Below it are input fields for 'Full Name', 'Password', 'Email Address', and 'Profile Group'. A checkbox for 'Allow password changes' is checked. To the right is a table of users:

Username	Full Name	Auth	Email	Profile	Mute Time
admin		local			1h 8h 1d 7d forever Edit
api-ro	api-ro	local			1h 8h 1d 7d forever Edit Delete
api-rw	api-rw	local			1h 8h 1d 7d forever Edit Delete
njc-test	Neil-Test	local		Profile-Asia-Pac	1h 8h 1d 7d forever Edit Delete
njf	Nick	local	nick@example.com	Profile-NetOps	1h 8h 1d 7d forever Edit Delete
temp-user	Temp User	local	temp-user@akips.com	Helpdesk	1h 8h 1d 7d forever Edit Delete

Graphic 4: configuring user settings for the config and events web API

Case study

A customer wanted to return data from the web API config and events endpoint in JSON. He used site scripting to loop through a list of devices and push the output to an array:

```
push(@deviceoutput, {devicename => $dev, ip4addr =>
$ip4addr, model => $model});
```

He then used the JSON library to convert the array to JSON format:

```
use JSON; my $jsonoutput = to_json(\@deviceoutput,
{utf8 => 1, pretty => 1, canonical => 1});
```

4.5.1 cURL

You can use cURL to access AKIPS data through the web API.

Command line options include:

Command line	Description
<code>-k</code>	insecure mode; suppresses SSC error messages
<code>-d, --data</code>	sends POST data
<code>--compressed</code>	notifies the HTTP server to compress output
<code>--data-binary</code>	sends POST data in binary form: does not strip new line characters (e.g. gzip)
<code>@{filename}</code>	reads POST data from {filename}. You must first use <code>-d, --data</code>
<code>@-</code>	reads POST data from standard input. You must first use <code>-d, --data</code>

Examples

Retrieve a list of devices:

```
curl "http://{server}/api-db?password={pw};cmds=mget+device+*"
```

Retrieve a list of unreachable IPv4 ping devices:

```
curl "http://{server}/api-db?password={pw};  
cmds=mget+***+ping4+PING.icmpState+value+/down/"
```

4.5.2 data

Use the `data` command to send data, including multiple commands at a time.

You can run several commands from a file, e.g.

```
curl --data-binary @commands  
"http://{server}/api-db?password={pw}"
```

You can run several commands from the standard input stream, e.g.

```
cat commands | curl --data-binary @-  
"http://{server}/api-db?password={pw}"
```

Examples

Retrieve a list of devices:

```
curl -d "cmds=mget device *"  
"http://{server}/api-db?password={pw}"
```

Retrieve a list of unreachable IPv4 ping devices:

```
curl -d "cmds=mget * * ping4 PING.icmpState value /down/"  
"http://{server}/api-db?password={pw}"
```

Chapter 5

Syslog and traps reporter

AKIPS stores all syslog and SNMP traps in a single database.

Use the `nm-msg-reporter` command line tool to extract and filter messages.

Use the following syntax:

```
time {filter}
```

```
[type {syslog|trap}]
```

```
[addr {filter}]
```

```
[limit {num}]
```

```
[regex {filter}]
```

```
[mute {file}]
```

```
[trim {file}]
```

```
[opt stats]
```

```
[interval {sec}]
```

5.1 CSV output

Each syslog or trap message contains:

- header line: {system timestamp} {type} {IP version} {IP Address}
- message text
- blank terminating line.

Examples

Retrieve all syslog messages for the past hour:

```
time last1h type syslog
```

```
1436229532 syslog 4 10.4.2.130
error local7 67: *Mar 3 09:22:52.269: SYS-3-CPUHOG: Task is
running for (3180)msecs, more ...
```

```
1436229532 syslog 4 10.4.2.130
error local7 68: -Traceback= 0x60C35A94 0x60C35C84 0x60C34688
0x60C34B84 0x60C38BC8 0x60C2950C ...
```

```
1436229532 syslog 4 10.4.2.130
error local7 69: *Mar 3 09:22:53.109: SYS-3-CPUHOG: Task is
running for (4024)msecs, more ...
```

```
1436229532 syslog 4 10.4.2.130
error local7 70: -Traceback= 0x60C35A98 0x60C35C84 0x60C34688
0x60C34B84 0x60C38BC8 0x60C2950C ...
```

Retrieve all trap messages for the past day which contain specific text:

```
type trap time lastId regex OSPF
```

```
1436232075 trap 4 10.4.2.26
SNMPv2-MIB sysUpTime 0 TimeTicks 53803
SNMPv2-MIB snmpTrapOID 0 ObjectIdentifier
CISCO-SYSLOG-MIB.clog MessageGenerated
CISCO-SYSLOG-MIB clogHistFacility 122 DisplayString OSPFv3
CISCO-SYSLOG-MIB clogHistSeverity 122 ENUM 6,notice
CISCO-SYSLOG-MIB clogHistMsgName 122 DisplayString ADJCHG
CISCO-SYSLOG-MIB clogHistMsgText 122 DisplayString Process 1, Nbr
10.4.45.1 on Serial1/6 from ...
CISCO-SYSLOG-MIB clogHistTimestamp 122 TimeTicks 53803
```

```
1436232075trap 4 10.4.2.26
SNMPv2-MIB sysUpTime 0 TimeTicks 53803
SNMPv2-MIB snmpTrapOID 0 ObjectIdentifier
OSPF-TRAP-MIB.ospf NbrStateChange
OSPF-MIB ospfRouterId 10.4.2.20 IPAddress 10.4.40.1
OSPF-MIB ospfNbrIpAddr 10.4.2.20 IPAddress 10.4.2.166
OSPF-MIB ospfNbrAddressLessIndex 10.4.2.20 Integer 0
OSPF-MIB ospfNbrRtrId 10.4.2.20 IPAddress 10.4.45.1
OSPF-MIB ospfNbrState 10.4.2.20 ENUM 1,down
```

Retrieve all syslog and trap messages for today from a specific IP address:

```
time today addr 10.4.2.26
```

```
1436232275 syslog 4 10.4.2.26
notice local7 149:Jul 7 11:24:34.476: LINEPROTO-5-UPDOWN: Line
protocol on Interface Serial1/6, changed...
```

```
1436232275 syslog 4 10.4.2.26
notice local7 150:Jul 7 11:24:34.572: OSPF-5-ADJCHG: Process 1,
Nbr 10.4.45.1 onSerial1/6 from LOADING...
```

```
1436232275 trap 4 10.4.2.26
SNMPv2-MIB sysUpTime 0 TimeTicks 54003
SNMPv2-MIB snmpTrapOID 0 ObjectIdentifier
OSPF-TRAP-MIB.ospf Nbr StateChange
OSPF-MIB ospfRouterId 10.4.2.20 IPAddress 10.4.40.1
OSPF-MIB ospfNbrIpAddr 10.4.2.20 IPAddress 10.4.2.166
OSPF-MIB ospfNbrAddressLessIndex 10.4.2.20 Integer 0
OSPF-MIB ospfNbrRtrId 10.4.2.20 IPAddress 10.4.45.1
OSPF-MIB ospfNbrState 10.4.2.20 ENUM 8,full
```

```
1436232276 trap 4 10.4.2.26
SNMPv2-MIB sysUpTime 0 TimeTicks 54004
SNMPv2-MIB snmpTrapOID 0 ObjectIdentifier
OSPF-TRAP-MIB. ospf OriginateLsa
OSPF-MIB ospfRouterId 10.4.2.20 IPAddress 10.4.40.1
OSPF-MIB ospfLsdbAreaId 10.4.2.20 IPAddress 0.0.0.0
OSPF-MIB ospfLsdbType 10.4.2.20 ENUM 1,routerLink
```

5.2 Web API

You can use a web API wrapper for `nm-msg-reporter`

Use the following syntax:

```
https://{server}/api-msg?password={pw};time={time filter};  
[addr={ip filter}];[type=syslog|trap];[device={name}|{regex}];  
[regex={regex filter}];[limit={qty messages}]
```

Examples

Retrieve all syslog messages for the past 30 minutes for devices with specific text:

```
http://{server}/api-msg?password={pw};time=last30m;type=syslog;  
device=/^swt/;
```

Retrieve up to a specific number of syslog messages for the past hour for a specific IP address:


```
http://{server}/api-msg?password={pw};time=last1h;addr=0.1.9.6;  
type=syslog;regex=down;limit=5;
```

To activate the syslog and traps web API:

Go to **Admin > API > Web API Settings**.

Click the **Syslog and Traps** option **On**.

Click **Save**.




Graphic 5: activating the syslog and traps web API

Go to **Admin > Users / Profiles > User Settings**.

In the **Username** text field, type `api-ro`

Complete the remaining text fields.

Click **Add**.



Graphic 6: configuring user settings for the syslog and traps web API

Chapter 6

Availability

Use the `nm-availability` command line tool to retrieve availability statistics.

Use the following syntax:

```
[-m] (include maintenance mode)  
mode { group | device | events }  
time { time filter }  
report { ping4,ping6,snmp,ifstatus }  
[entity { device } [{ interface }]]  
[group { name }]  
[profile { name }]
```

6.1 Group

This will retrieve a summary of device and interface groups.

The output will be in the following format:

```
{child},{attr},{group name},{total time},{match time},  
{group target},{tf}[:{group tf}]
```

Example

```
nm-availability mode group time last1w report ping4
```

```
ping4,PING.icmpState,1-Building-4,11688115,11687711,9990,last1w  
ping4,PING.icmpState,1-Fraser,8213270,8213190,9990,last1w  
ping4,PING.icmpState,1-Building-16,44541195,44540002,9990,last1w  
ping4,PING.icmpState,Accedian,1766635,1766635,9890,last1w;  
mon to sat 6:00 to 20:00  
ping4,PING.icmpState,Aerohive,589475,589475,9999,last1w;  
mon to fri 7:00 to 19:00; sat 8:00 to 18:00
```

6.2 Device

This will retrieve a summary of devices.

The output will be in the following format:

```
{parent},{child},{attr},{total time},{match time},{group target}
```

Example

```
nm-availability mode device time last1w report snmp,ping4  
group Accedian
```

```
accedian-131-2-7,ping4,PING.icmpState,136020,136020,9890  
accedian-131-2-7,sys,SNMP.snmpState,136020,136020,9890  
accedian-131-2-8,ping4,PING.icmpState,136020,136020,9890  
accedian-131-2-8,sys,SNMP.snmpState,136020,136020,9890  
accedian-131-2-9,ping4,PING.icmpState,136020,136020,9890  
accedian-131-2-9,sys,SNMP.snmpState,136020,136020,9890
```

6.3 Events

This will retrieve pairs of up/down events.

The output will be in the following format:

```
{parent},{child},{down},{up},{total time},{match_time}
```

Example

```
nm-availability mode events time last1M report ping4  
entity cisco-131-16-1
```

```
cisco-131-16-1,ping4,1603822871,1603822916,2389764,2388341  
cisco-131-16-1,ping4,1603088563,1603089823,2389764,2388341  
cisco-131-16-1,ping4,1603060380,1603060498,2389764,2388341
```

Chapter 7

NetFlow reporter

AKIPS stores NetFlow records in a dedicated database.

Use the `nm-flow-reporter` command line tool to query the database.

Use the following syntax:

```
nm-flow-reporter [optional parameters] time {time filter}  
exporter {exporter IP address}
```

Optional parameters:

```
[src_ip | dst_ip | any_ip | both_ip {IP filter}]
```

```
[src_as | dst_as | any_as | both_as {AS Number|Name|Regex}]
```

```
[src_idx | dst_idx | any_idx | both_idx {ifIndex}]
```

```
[show src_ip,dst_ip,src_host,dst_host,src_idx,dst_idx,src_as,  
dst_as,geo,tos,proto,pkt,oct,flow,conv,tsf,url]
```

```
[sort src_ip | dst_ip | src_idx | dst_idx | src_as | dst_as |  
pkt | oct | flow | conv]
```

```
[proto {protocol.service}]
```

```
[limit {num}]
```

```
[sort_dir {f | r}]
```

Parameter	Description
<code>src_ip</code>	source IPv4/6 address
<code>dst_ip</code>	destination IPv4/6 address
<code>src_idx</code>	SNMP index of source (input) interface
<code>dst_idx</code>	SNMP index of destination (output) interface
<code>src_host</code>	source hostname
<code>dst_host</code>	destination hostname
<code>src_as</code>	source AS number
<code>dst_as</code>	destination AS number
<code>geo</code>	location (country code) of IP addresses
<code>tos</code>	IP type of service
<code>proto</code>	IP protocol type
<code>pkt</code>	number of packets
<code>oct</code>	octets (bytes)
<code>flow</code>	flows

(continued)

Parameter	Description
<code>conv</code>	number of conversations
<code>tsf</code>	filter that can be passed to <code>nm-flow-timeseries</code>

Example

Retrieve TopN protocol data for packets/octet, sorted by octets:

```
http://{server}/api-flow?password={pw};exporter=10.0.0.254;  
time=last10m;show=proto,pkt,oct;sort=oct
```

7.1 CSV output

The first line of output contains 24 fields which describe the data. Each following line contains data which match the parameters. Empty fields represent an unreported value.

```
source IP,destination IP,source index,destination index,
source hostname,destination hostname,source AS number,
destination AS number,source AS name,destination AS name,
source location,destination location,type of service,protocol,
packets,octets,flows,conversations,timeseries filter,url,
milliseconds to process,records processed,records matched,
records included in result
```

Example

```
nm-flow-reporter exporter 10.117.0.35 time last30m limit 10show
src_ip,dst_ip,proto,geo,tos,pkt,oct,flow sort pktsort_dir f
src_ip 188.24.60.104 #Src IP,Dst IP,,,,,Src Location,Dst
Location,TOS Number,Protocol,
Packets,Bytes,Flows,,,3,44346,221,213

188.24.60.104,213.138.70.62,,,,,,R0,RU,0,tcp.re-mail-ck,124,
74576,3,,
188.24.60.104,203.45.91.4,,,,,,R0,AU,0,icmp.echoreply,73,38921,2,,
188.24.60.104,65.60.39.90,,,,,,R0,US,0,udp.epmap,64,38303,2,,
188.24.60.104,65.60.39.90,,,,,,R0,US,0,udp.unknown,63,33321,2,,
188.24.60.104,58.167.215.31,,,,,,R0,AU,0,tcp.http,49,35703,1,,
188.24.60.104,202.159.32.2,,,,,,R0,ID,200,udp.domain,49,29878,1,,
188.24.60.104,203.45.91.4,,,,,,R0,AU,0,udp.z3950,49,35131,1,,
188.24.60.104,123.100.150.72,,,,,,R0,AU,0,tcp.timeserver,49,
31455,1,,
188.24.60.104,81.205.200.183,,,,,,R0,NL,0,tcp.snpp,48,20521,1,,
188.24.60.104,65.60.39.90,,,,,,R0,US,0,tcp.netbios-ns,48,12403,1,,
```

7.2 Web API

You can use a web API wrapper for `nm-flow-reporter`

Use the following syntax:

```
http://{server}/api-flow?password={pw};{option}={value};...
```

Option	Value
<code>exporter</code>	<code>{exporter IP}</code>
<code>time</code>	<code>{increments of 5 minutes}</code>
<code>show</code>	<code>src_ip,dst_ip,src_host,dst_host,src_idx, dst_idx,src_as,dst_as,geo,tos,proto,pkt, oct,flow,conv</code>
<code>sort</code>	<code>src_ip dst_ip src_idx dst_idx src_as dst_as pkt oct flow conv</code>
<code>proto</code>	<code>{protocol}.{service}</code>
<code>src_ip dst_ip any_ip both_ip</code>	<code>{ip filter}</code>
<code>src_as dst_as any_as both_as</code>	<code>{Autonomous System Filter}</code>
<code>src_idx dst_idx any_idx both_idx</code>	<code>{Index Filter Number}</code>
<code>sort_dir</code>	<code>f r</code>

To activate the NetFlow web API:

Go to **Admin > API > Web API Settings**.

Click the **NetFlow** option **On**.

Click **Save**.

AKIPS Dashboards Reports Tools Admin **New** PDF Licensed to demo1 v21.7.1 User: admin

Web API Settings

Availability Off
Default: off

Config and Events On
Default: off

Config Viewer On
Default: off

HTTP Log Off
Default: off

NetFlow On
Default: off

NetFlow Time-series Off
Default: off

Site Script Functions On
Default: off

Switch Port Mapper On
Default: off

Syslog and Traps On
Default: off

Unused Interfaces On
Default: off

Save

Availability

This is a Web API wrapper around the nm-availability program. Refer to the AKIPS programming guide.

Access:
Requires a username of `api-ro`

Syntax:
`http://(server)/api-availability?password=(pw);(option)=(value);...`

Options:

Option	Value	Comment
maintenance	on off	Show/hide maintenance mode devices
mode	group device events	One only
time	{time filter}	Refer to the programming guide
report	ping4, ping6, snmp, ifstatus	Any combination, comma separated
entity	{device} {child}	
group	{group_name}	
profile	{profile_name}	

Example:
`http://(server)/api-availability?password=(pw),mode=group,time=last1d,report=ping4`

Sample Output:

```
ping4,PING,icmpState,Cisco,817150,815400,10000,last1d
ping4,PING,icmpState,FreeBSD,5832,5832,9500,last1d
```

Config and Events

This is a Web API wrapper around the nm-db program. Refer to the *API Programming Guide*.

Access:
Requires a username of `api-ro` and/or `api-rw`.

Username	Permissions
api-ro	Read-only commands
api-rw	All commands


Graphic 7: activating the NetFlow web API

Go to **Admin > Users / Profiles > User Settings**.

In the **Username** text field, type `api-ro`

Complete the remaining text fields.

Click **Add**.



The screenshot shows the 'User Settings' page in the AKiPS interface. The 'Username' field is highlighted with a red box and contains the text 'api-ro'. Below the form, there is a table of existing users.

Username	Full Name	Auth	Email	Profile	Mute Time	
admin		local			1h 8h 1d 7d forever	Edit
api-ro	api-ro	local			1h 8h 1d 7d forever	Edit Delete
api-rw	api-rw	local			1h 8h 1d 7d forever	Edit Delete
njc-test	Neil-Test	local		Profile-Asia-Pac	1h 8h 1d 7d forever	Edit Delete
njf	Nick	local	nick@example.com	Profile-NetOps	1h 8h 1d 7d forever	Edit Delete
temp-user	Temp-User	local	temp-user@akips.com	Helpdesk	1h 8h 1d 7d forever	Edit Delete

Graphic 8: configuring user settings for the NetFlow web API

Chapter 8

NetFlow time series

Use the `nm-flow-timeseries` command line tool to extract time-series values for:

- packets
- bytes (octets)
- bits per second
- flows.

Use the following syntax:

```
nm-flow-timeseries [optional parameters] time {time filter}  
exporter {exporter IP address} interval {minutes}
```

Optional parameters:

```
[src_ip | dst_ip | any_ip | both_ip {IP filter}]  
[src_as | dst_as | any_as | both_as {AS Number|Name|Regex}]  
[src_idx | dst_idx | any_idx | both_idx {ifIndex}]  
tos {number} [proto {protocol.service}]
```

8.1 CSV output

Each query delivers four lines of CSV output that may contain the following:

- **source/destination IP**
- **protocol**
- **start time** (POSIX timestamp)
- **interval in seconds**
- **time-series values.** AKIPS calculates these by dividing the time span by the interval. E.g. today divided by 60 minutes produces 24 time-series values.

Examples

```
time last1h src_ip 157.187.62.203 interval 10 exporter
172.16.1.17
```

```
157.187.62.203,,,,Pkts,1436243100,600,69970,1236,44698,45,38252,
33,21
157.187.62.203,,,,Bytes,1436243100,600,98279249,134122,62765460,
4296,53683296,3352,2009
157.187.62.203,,,,Bits 1436243100,600,786233992,1072976,502123680,
34368,429466368,26816,16072
157.187.62.203,,,,Flows,1436243100,600,32,41,30,45,38,31,21
```

```
time last1h src_ip 10.1.8.62 proto udp.snmp interval 5 exporter
10.4.2.22
```

```
10.1.8.62,,,udp.snmp,Pkts,1436244300,300,126,114,125,128,495,125,
128,106,131,128,121,0,52
10.1.8.62,,,udp.snmp,Bytes,1436244300,300,76605,68846,75615,77655,
120197,75738,77745,64000,79708,...
10.1.8.62,,,udp.snmp,Bits,1436244300,300,612840,550768,604920,
621240,961576,605904,621960,512000,...
10.1.8.62,,,udp.snmp,Flows,1436244300,300,49,51,50,50,140,50,50,
48,52,50,22,0,16
```

8.2 Web API

You can use a web API wrapper for `nm-flow-timeseries`

Use the following syntax:

```
http://{server}/api-flow-timeseries?password={pw};  
{option}={value};...
```

Option	Value
<code>exporter</code>	<code>{exporter IP}</code>
<code>time</code>	<code>{time filter}</code>
<code>interval</code>	<code>{increments of 5 minutes}</code>
<code>proto</code>	<code>{protocol}.{service}</code>
<code>src_ip dst_ip any_ip both_ip</code>	<code>{ip filter}</code>
<code>src_as dst_as any_as both_as</code>	<code>{AS Number Name Regex}</code>
<code>src_idx dst_idx any_idx both_idx</code>	<code>{ifIndex}</code>
<code>tos</code>	<code>{number}</code>

Example

Retrieve five-minute time-series values for all flow records on a specific exporter:

```
http://{server}/api-flow-timeseries?password={pw};
exporter=10.0.0.254;time=last4h;interval=5
```

To activate the NetFlow time-series web API:

Go to **Admin > API > Web API Settings**.

Click the **NetFlow Time-series** option **On**.

Click **Save**.

The screenshot shows the AKIPS Web API Settings page. The 'NetFlow Time-series' option is highlighted with a red box and is set to 'On'. The page also displays settings for 'Availability' and 'Config and Events'.

Web API Settings

- Availability: Off (Default: off)
- Config and Events: On (Default: off)
- Config Viewer: On (Default: off)
- HTTP Log: Off (Default: off)
- NetFlow: On (Default: off)
- NetFlow Time-series: On (Default: off)
- Site Script Functions: On (Default: off)
- Switch Port Mapper: On (Default: off)
- Syslog and Traps: On (Default: off)
- Unused Interfaces: On (Default: off)

Availability

This is a Web API wrapper around the nm-availability program. Refer to the AKIPS programming guide.

Access: Requires a username of `api-ro`

Syntax: `http://{server}/api-availability?password={pw};(option)={value};...`

Options:

Option	Value	Comment
maintenance	on off	Show/hide maintenance mode devices
mode	group device events	One only
time	{time filter}	Refer to the programming guide
report	ping4, ping5, snmp, ifstatus	Any combination, comma separated
entity	{device} {{child}}	
group	{group_name}	
profile	{profile_name}	

Example: `http://{server}/api-availability?password={pw};mode=group;time=last1d;report=ping4`

Sample Output:

```
ping4,PING. icmpState,Cisco,817150,815400,10000,last1d
ping4,PING. icmpState,FreeBSD,5832,5832,9500,last1d
```

Config and Events

This is a Web API wrapper around the nm-db program. Refer to the *API Programming Guide*.

Access: Requires a username of `api-ro` and/or `api-rw`.

Username	Permissions
api-ro	Read-only commands
api-rw	All commands

Save


Graphic 9: activating the NetFlow time series web API

Go to **Admin > Users / Profiles > User Settings**.

In the **Username** text field, type `api-ro`

Complete the remaining text fields.

Click **Add**.



The screenshot shows the AKiPS User Settings interface. The 'Username' field is highlighted with a red box and contains the text 'api-ro'. Below the form fields is a table of existing users.

Username	Full Name	Auth	Email	Profile	Mute Time	
admin		local			1h 8h 1d 7d forever	Edit
api-ro	api-ro	local			1h 8h 1d 7d forever	Edit Delete
api-rw	api-rw	local			1h 8h 1d 7d forever	Edit Delete
njc-test	Neil-Test	local		Profile-Asia-Pac	1h 8h 1d 7d forever	Edit Delete
njf	Nick	local	nick@example.com	Profile-NetOps	1h 8h 1d 7d forever	Edit Delete
temp-user	Temp-User	local	temp-user@akips.com	Helpdesk	1h 8h 1d 7d forever	Edit Delete

Graphic 10: configuring user settings for the NetFlow time series web API

Chapter 9

Switch port mapper

Switch port mapper data is stored in CSV format.

You can access it via:

- the command console (see 2.2)
- system log viewer (Go to **Admin > System > System Log Viewer**)
- web API (see 9.2).

9.1 CSV output

Filename	Description	Output format (CSV)
arp	ARP tables	<code>epoch,ipaddress,mac</code>
ip2mac	IP to MAC mapping	<code>epoch,mac,ipaddress</code>
mac2ip	MAC to IP mapping	<code>epoch,mac,ipaddress</code>
mac2sp	MAC to switch interface mapping	<code>epoch,mac, switch,port</code>
mac2vspa	MAC to vendor, switch, interface, IP address	<code>mac,vendor,switch, port,ipaddress</code>
sp2mac	switch interface to MAC	<code>switch,port,mac</code>
sp2vlan	switch interface to VLAN	<code>epoch,switch, port,vlan</code>
vlan2sp	VLAN to switch interface	<code>epoch,vlan, switch,port</code>
vlans	list of all VLANs	<code>vlan</code>

9.2 Web API

To activate the switch port mapper web API:

Go to **Admin > API > Web API Settings**.

Click the **Switch Port Mapper** option **On**.

Click **Save**.

The screenshot shows the AKiPS Web API Settings page. The 'Switch Port Mapper' option is highlighted with a red box and is set to 'On'. The page includes a sidebar with various settings, a main content area with instructions and a table of options, and a 'Save' button at the bottom.

Web API Settings

Availability Off
Default: off

Config and Events On
Default: off

Config Viewer On
Default: off

HTTP Log Off
Default: off

NetFlow Off
Default: off

NetFlow Time-series Off
Default: off

Site Script Functions On
Default: off

Switch Port Mapper On
Default: off

Syslog and Traps On
Default: off

Unused Interfaces On
Default: off

Save

Availability

This is a Web API wrapper around the nm-availability program.
Refer to the AKiPS programming guide.

Access:
Requires a username of `api-ro`

Syntax:
`http://(server)/api-availability?password=(pw);(option)=(value);...`

Options:

Option	Value	Comment
<code>maintenance</code>	<code>on off</code>	Show/hide maintenance mode devices
<code>mode</code>	<code>group device events</code>	One only
<code>time</code>	<code>{time filter}</code>	Refer to the programming guide
<code>report</code>	<code>ping4, ping6, snmp, ifstatus</code>	Any combination, comma separated
<code>entity</code>	<code>{device} [{child}]</code>	
<code>group</code>	<code>{group_name}</code>	
<code>profile</code>	<code>{profile_name}</code>	

Example:
`http://(server)/api-availability?password=(pw).mode=group;time=lastId;report=ping4`

Sample Output:

```
ping4,PING.icmpState,Cisco,817150,815400,10000,lastId
ping4,PING.icmpState,FreeBSD,5832,5832,9500,lastId
```

Config and Events

This is a Web API wrapper around the nm-db program.
Refer to the *API Programming Guide*.

Access:
Requires a username of `api-ro` and/or `api-rw`.

Username	Permissions
<code>api-ro</code>	Read-only commands
<code>api-rw</code>	All commands

Graphic 11: activating the switch port mapper web API

Go to **Admin > Users / Profiles > User Settings**.

In the **Username** text field, type `api-ro`

Complete the remaining text fields.

Click **Add**.

The screenshot shows the AKiPS User Settings page. The top navigation bar includes 'Dashboards', 'Reports', 'Tools', 'Admin', 'New', and 'PDF'. The user is logged in as 'admin'. The page title is 'User Settings'. On the left, there is a form for adding a new user with the following fields: Username (set to 'api-ro'), Full Name, Password, a checked 'Allow password changes' checkbox, Email Address, and Profile Group. An 'Add' button is at the bottom of the form. On the right, there is a table of existing users.

Username	Full Name	Auth	Email	Profile	Mute Time	
admin		local			1h 8h 1d 7d forever	Edit
api-ro	api-ro	local			1h 8h 1d 7d forever	Edit Delete
api-rw	api-rw	local			1h 8h 1d 7d forever	Edit Delete
njc-test	Neil-Test	local		Profile-Asia-Pac	1h 8h 1d 7d forever	Edit Delete
njf	Nick	local	nick@example.com	Profile-NetOps	1h 8h 1d 7d forever	Edit Delete
temp-user	Temp-User	local	temp-user@akips.com	Helpdesk	1h 8h 1d 7d forever	Edit Delete

Graphic 12: configuring user settings for the switch port mapper web API

Chapter 10

Unused interfaces

10.1 CSV output

Field	Description
1	device name
2	interface name
3	interface speed
4	used/free
5	current IF-MIB.ifOperStatus
6	last change time (epoch timestamp (seconds))
7	IF-MIB.ifAlias
8	VLAN name

10.2 Web API

To activate the unused interfaces web API:

Go to **Admin > API > Web API Settings**.

Click the **Unused Interfaces** option **On**.

Click **Save**.

AKiPS Dashboards Reports Tools Admin **New** PDF Licensed to demo1 v21.7.1 User: admin

Web API Settings

Availability Off Default: off

Config and Events On Default: off

Config Viewer On Default: off

HTTP Log Off Default: off

NetFlow Off Default: off

NetFlow Time-series Off Default: off

Site Script Functions On Default: off

Switch Port Mapper On Default: off

Syslog and Traps On Default: off

Unused Interfaces On Default: off

Save

Availability

This is a Web API wrapper around the nm-availability program. Refer to the AKiPS programming guide.

Access:
Requires a username of `api-ro`

Syntax:
`http://(server)/api-availability?password=(pw);(option)=(value);...`

Options:

Option	Value	Comment
<code>maintenance</code>	<code>on off</code>	Show/hide maintenance mode devices
<code>mode</code>	<code>group device events</code>	One only
<code>time</code>	<code>{time filter}</code>	Refer to the programming guide
<code>report</code>	<code>ping4, ping6, snmp, ifstatus</code>	Any combination, comma separated
<code>entity</code>	<code>{device} [{child}]</code>	
<code>group</code>	<code>{group_name}</code>	
<code>profile</code>	<code>{profile_name}</code>	

Example:
`http://(server)/api-availability?password=(pw).mode=group;time=lastId;report=ping4`

Sample Output:

```
ping4,PING.icmpState,Cisco,817150,815400,10000,lastId
ping4,PING.icmpState,FreeBSD,5832,5832,9500,lastId
```

Config and Events

This is a Web API wrapper around the nm-db program. Refer to the *API Programming Guide*.

Access:
Requires a username of `api-ro` and/or `api-rw`.

Username	Permissions
<code>api-ro</code>	Read-only commands
<code>api-rw</code>	All commands

Graphic 13: activating the unused interfaces web API

Go to **Admin > Users / Profiles > User Settings**.

In the **Username** text field, type `api-ro`

Complete the remaining text fields.

Click **Add**.

The screenshot shows the 'User Settings' page in the AKiPS application. The 'Username' field is highlighted with a red box and contains the text 'api-ro'. Below the form fields is a table of existing users. The 'Add' button is visible at the bottom of the form.

Username	Full Name	Auth	Email	Profile	Mute Time	
admin		local			1h 8h 1d 7d forever	Edit
api-ro	api-ro	local			1h 8h 1d 7d forever	Edit Delete
api-rw	api-rw	local			1h 8h 1d 7d forever	Edit Delete
njc-test	Neil-Test	local		Profile-Asia-Pac	1h 8h 1d 7d forever	Edit Delete
njf	Nick	local	nick@example.com	Profile-NetOps	1h 8h 1d 7d forever	Edit Delete
temp-user	Temp-User	local	temp-user@akips.com	Helpdesk	1h 8h 1d 7d forever	Edit Delete

Graphic 14: configuring user settings for the unused interfaces web API

Chapter 11

TCP socket

You can use the TCP socket daemon to remotely access `nm-db` and `nm-msg-reporter`

It does not perform authentication, so use it only in a secure environment.

Use the following syntax:

```
{program} {socket number} [{Restrict IP Address}]
```

Examples

Start an `nm-db` process listening on a port:

```
nm-db 3000
```

Start an `nm-db` process listening on a port and allow connections from a specific IP address:

```
nm-db 3001 10.0.0.50
```

Start an `nm-msg-reporter` process listening on a port and allow connections from a specific IP address:

```
nm-msg-reporter 3002 10.0.0.51
```

Chapter 12

Perl modules

12.1 Common

This module is located in `/usr/local/akips/pm/Akips/Common.pm`

Review the module for available definitions and externally visible functions.

12.1.1 Useful arrays

```
@weekday_names_short = (  
    "Sun", "Mon", "Tue", "Wed", "Thu", "Fri", "Sat", "Sun"  
);  
  
@weekday_names_long = (  
    "Sunday", "Monday", "Tuesday", "Wednesday", "Thursday",  
    "Friday", "Saturday", "Sunday"  
);  
  
@month_names_short = (  
    "Jan", "Feb", "Mar", "Apr", "May", "Jun", "Jul", "Aug",  
    "Sep", "Oct", "Nov", "Dec"  
);  
  
@month_names_long = (  
    "January", "February", "March", "April", "May", "June",  
    "July", "August", "September", "October",  
    "November", "December"  
);  
  
@days_of_month = (  
    "1st", "2nd", "3rd", "4th", "5th", "6th", "7th", "8th", "9th",  
    "10th", "11th", "12th", "13th", "14th", "15th", "16th",  
    "17th", "18th", "19th", "20th", "21st", "22nd", "23rd",  
    "24th", "25th", "26th", "27th", "28th", "29th", "30th", "31st"  
);  
  
@days_in_month = (  
    31, 28, 31, 30, 31, 30, 31, 31, 30, 31, 30, 31  
);  
  
@metric_prefix = (  
    'p', 'n', 'u', 'm', '', 'K', 'M', 'G', 'T', 'P', 'E'  
);
```

12.1.2 PRINT_LINE

PRINT_LINE is useful when debugging.

It prints the following on a single line to stderr:

- date/time
- process name
- function name
- filename
- line number
- error message.

Example

```
Jan 6 13:20:51.583957 0 ms nm-site-script-alert_uplink 44232
Akips::Site::alert_uplink Site.pm:48
Service returned: "401 Unauthorized"
```

12.1.3 trim

trim strips white space (spaces, line breaks, etc) from a string.

Example

```
my $str = " Hello World ! ";
$str = trim ($str);
print ($str); # "Hello World!"
```

12.1.4 errlog

AKIPS uses its own error log.

Use the following syntax:

```
errlog ({LOG_LEVEL}, {log message});
```

Available log levels:

```
$ERR_FATAL
```

```
$ERR_ERROR
```

```
$ERR_WARNING
```

```
$ERR_INFO
```

```
$ERR_USER
```

```
$ERR_DEBUG
```

```
$ERR_CGI
```

Example

```
my $error_msg = "it broke";  
errlog ($ERR_FATAL, "something went wrong - %s",  
$error_msg);
```

To view error messages:

Go to **Admin > System > System Log Viewer**.

12.1.5 `get_localtime()`

`get_localtime()` (epoch timestamp) is a wrapper around the standard `localtime()`

Element	Description
<code>\$hash{sec}</code>	seconds: 00 to 59
<code>\$hash{min}</code>	minutes: 00 to 59
<code>\$hash{hour}</code>	hours: 00 to 23
<code>\$hash{wday}</code>	day of the week: 0 = Sunday to 6 = Saturday
<code>\$hash{mday}</code>	day of the month: 1 to 31
<code>\$hash{mon}</code>	month: 0 = January to 11 = December
<code>\$hash{year}</code>	year, e.g. 2020
<code>\$hash{yday}</code>	day of the year: 0 to 364 (0 to 365 in leap years)
<code>\$hash{isdst}</code>	daylight saving time: 0 = No, 1 = Yes

Example

```
my $h_ref = get_localtime ();

printf STDOUT "%s %s %s",
    $days_of_month[$h_ref->{mday} - 1],
    $month_names_long[$h_ref->{mon}],
    $h_ref->{year};
```

12.1.6 mail()

mail() takes a hash reference containing:

- to
- subject
- body.

Example

```
my @body = (  
    "Hello,",  
    "Greetings from AKIPS!",  
    "Sincerely,",  
    "Bob"  
);  
  
@files = ("/path/to/graph1.png", "/path/to/report1.pdf",  
"/path/to/report2.pdf");  
  
mail ({  
    to      => 'admin@example.com',  
    subject => 'Greetings',  
    body    => \@body,  
    attach  => \@files, #(optional)  
});
```

12.1.7 syslog()

Element	Description	Options
<code>ipaddr</code>	destination IP address	
<code>priority</code>	default: notice	<code>emergency alert critical error warning notice info debug</code>
<code>facility</code>	default: user	<code>auth authpriv console cron daemon ftp kern lpr mail news ntp security syslog user uucp local0 local1 local2 local3 local4 local5 local6 local7</code>
<code>message</code>	message body	

Example

```
syslog ({  
    ipaddr    = > "10.50.1.100",  
    priority  = > "error",  
    facility  = > "local3",  
    message   = > "The quick brown fox has jumped",  
});
```

12.1.8 `http_send()` and `http_result()`

These HTTP functions are a wrapper around the `nm-http` command line tool.

`http_send()` sends an HTTP request.

`http_result()` sends an HTTP request and returns response data.

Element	Value	Comment
<code>url</code>	<code>http://www.example.com</code>	HTTP
<code>method</code>	GET, HEAD, POST, PUT, DELETE, CONNECT, OPTIONS, TRACE, PATCH	case insensitive
<code>content_type</code>	<code>text/html</code>	<code>application/x-www-form-urlencoded</code> = default
<code>headers</code>		send custom HTTP headers
<code>proxy</code>	<code>host:port</code>	send request through the specified proxy
<code>secure</code>	0 or 1	0 = allow SSC 1 = default
<code>show_headers</code>	0 or 1	0 = default 1 = show headers
<code>data</code>	POST data	

12.2 AKIPS database

The command line tool for the ADB is `nm-db`.

The ADB module simplifies interacting with `nm-db` by automatically opening and closing a bidirectional pipe when loading and exiting.

12.2.1 `adb_send()`

Use `adb_send()` to write the specified command to `nm-db`.

Example

```
adb_send ("add device group CoreRouters");  
adb_send ("add device group CoreSwitches"); adb_flush ();
```

12.2.2 `adb_flush()`

Use `adb_flush()` to flush all buffered output to `nm-db`.

You must do this after calling `adb_send()`

12.2.3 `adb_result()`

Use `adb_result()` to write to `nm-db` and return the results in either a scalar or array.

You do not need to call `adb_flush()`

12.3 Discover

12.3.1 `discover_scan()`

`discover_scan()` performs the first stage of the device discover and creates the intermediate files for `discover_config()`

`ping.scan` lists the IPv4/6 addresses that responded to a ping scan.

`snmp.scan` lists the SNMP walk of the SNMPv2-MIB.system for each device.

`devices` lists the IPv4/6 address, SNMPv2-MIB.sysName, SNMP credentials, SNMPv2-MIB.sysObjectID and SNMPv2-MIB.sysDescr.

Use the following syntax:

```
discover_scan ( {SNMP Parameters}, {IP Address Range}, ... );
```

Examples

Scan three IP ranges using existing discover SNMP credentials:

```
discover_scan (undef, "10.0.0.0/16", "10.3.0.0/24",  
"10.5.0.0/24");
```

Scan multiple IP ranges using specified SNMPv2 credentials:

```
discover_scan ("version 2 community loofah", "10.3.0.0/24",  
"10.5.0.0/24");
```

Scan one IP address using specified SNMPv3 credentials:

```
discover_scan ("version 3 sha passwd1 aes256 passwd1",  
"10.2.0.1");
```

12.3.2 `discover_config()`

`discover_config()` performs SNMP walks of each device which `discover_scan()` locates, then processes the data to configure each device.

12.3.3 `discover_device_rewalk()`

`discover_device_rewalk()` performs an SNMP walk for a specified device and then processes the data to configure the device.

It returns:

0 = failure

1 = success

Use the following syntax:

```
discover_device_rewalk (%hash_ref);
```

Example

```
discover_device_rewalk ({  
    ipaddr = > "10.1.2.3",  
    device = > "atlanta-ro",  
})
```

Chapter 13

Site scripts

You can use site scripts to:

- configure AKIPS after discover
- configure AKIPS after auto grouping
- schedule periodic scripting.

Case study

A customer built a custom report in AKIPS by using fields in existing reports.

He used site scripting to load up arrays as `mget` outputs, added the necessary logic to align the data into hashes or whatever nested structure by whatever key fields, and then within a loop did a `printf` to produce a csv output.

He used smaller scripts with the `custom_ script` prefix to break them into more digestible and reusable subroutines, e.g. a function that only made DB calls.

13.1 Using site scripts

To use site scripts:

Go to the AKIPS website (<https://www.akips.com>).

Go to **Support > Site Scripts**.

To use an existing site script:

Copy the relevant script.

Open AKIPS and go to **Admin > API > Site Scripting**.

Paste the script into the text field.

To create a new site script:

Copy an existing AKIPS script which is similar to what you need.

Open AKIPS and go to **Admin > API > Site Scripting**.

Paste the script into the text field.

Modify the script.



[FEATURES](#) [RESOURCES](#) [SUPPORT](#) [DOWNLOAD](#) [COMPANY](#)

24. Interface Speeds by Name

This script manually sets interface speeds by specifying *device name* and *interface name*.

Site Scripting uses function names starting with `ifspeed_` to run commands to manually set interface speeds.

You can test your `ifspeed_code` by selecting "All ifspeed_functions" from the dropdown, then clicking **Run**. Make sure there are no error messages in the output on the right side of the screen. You can then check an Interface report to confirm that the speed has been set correctly.

If you only need to manually set speeds on a handful of interfaces, you can issue individual `set` commands specifying the device and interface names. The following example sets the speed to 2Gbps for 3 interfaces on the device `atlanta-ro`.

[Download script](#)

```

sub ifspeed_interfaces
{
  # Command syntax:
  # set {device} {interface} IF-MIB.ifSpeed = {speed in bits per sec}

  adb_send ("set atlanta-ro Te3/1 IF-MIB.ifSpeed = 2000000000");
  adb_send ("set atlanta-ro Te3/2 IF-MIB.ifSpeed = 2000000000");
  adb_send ("set atlanta-ro Te3/3 IF-MIB.ifSpeed = 2000000000");
  adb_flush ();
}
                    
```



Graphic 15: selecting and copying a site script



[Dashboards](#) [Reports](#) [Tools](#) [Admin](#) [New](#) [PDF](#)

Licensed to demo1 v21.7.1 User: admin

Site Scripting
Run
Save
Help

Site Scripting

NOTE: This is an "expert" only section. Assistance from AKiPS technical support may be required.

Site scripting is for performing:

- Post discover configuration
- Post auto grouping configuration
- Periodic scheduled scripting

Function names must start with the following prefixes, and will run at the times listed below.

Function name prefix	Schedule
alert_	Called by Alerting rules
config_	End of Discover/Rewalk
custom_	Manually via Site Scripting
group_	End of Discover/Rewalk or Auto Grouping
ifspeed_	End of Discover/Rewalk or Tune Interface Speed script
sched_min	Every N minutes (e.g. sched_15m_do_stuff)
sched_hh	Every N hours (e.g. sched_1h_do_more_stuff)
sched_HHMM	Run at a scheduled time (e.g. sched_0930_report)
web_	Remote http/https client

NOTES

- All functions are built into a single Perl module.
- Locking ensures only one instance of each type can run.
- Functions are run in order.

Alert Scripting

Alerting can use the `call` syntax to call a function in Site Scripting. The parameters passed through to the function vary depending on the type of alert (Status, Syslog, Threshold, or Trap).

The parameters are passed in via a hash reference, as per the following example:

```

adb alert_ifoperstatus_upLink
{
  my ($arg_ref) = @_;
  my $device = $arg_ref->{device};

  # ... code goes here ...
}
                    
```

```

1385 (
1386   my $IN;
1387   my $OUT;
1388   my $smmp_cfg_ref = config_load_smmp_cfg ();
1389   my $smmp_pid = spawn ($IN, $OUT, $SMMP_PROG) or EXIT_FATAL ("Can't start smmp process: $!");
1390   my $domains = config_load_domains ();
1391   my $ip2dev;
1392
1393   for my $line (adb_result ("get text + sys SNMP.ipaddr")) {
1394     my ($device, undef, undef, undef, $ipaddr) = split (" ", $line, 5);
1395     $ip2dev{$ipaddr} = $device;
1396   }
1397
1398   for my $ip (sort keys %$ip2dev) {
1399     my $device = $ip2dev{$ip};
1400     my $smmp_param = $smmp_cfg_ref->{lc ($device)}{cmd} || "";
1401     printf $OUT "get %s %s SNMPv2-MIB.sysName:0\n", $ip, $smmp_param;
1402   }
1403   close $OUT;
1404
1405   my @del_devices;
1406   while (my $line = <$IN>) {
1407     chomp $line;
1408     my ($ip, undef, undef, undef, $sysname) = split (" ", $line, 5);
1409     my $device = $ip2dev{$ip};
1410     next if (not defined $device);
1411     next if (not defined $sysname);
1412     $sysname = config_strip_sysname ($sysname, $domains);
1413     if ($device ne $sysname) {
1414       printf "Device name %s mismatch sysname %s\n", $device, $sysname;
1415       push @del_devices, $device;
1416     }
1417   }
1418   close $IN;
1419   rconfig_delete_device (@del_devices);
1420 }
1421
1422
1423
1424
1425
1426
                    
```



Graphic 16: pasting a site script into AKiPS

Click **Save**. AKIPS will kill the script if it runs for longer than two minutes.

Refresh the page.

The drop-down list will display functions which you can manually run from this page.

13.2 Naming a site script

When naming a script, use one of the following prefixes:

Prefix	Schedule
<code>admin_</code>	called by alerting rules
<code>config_</code>	end of discover/rewalk
<code>custom_</code>	manual execution
<code>group_</code>	end of discover/rewalk or auto grouping
<code>ifspeed_</code>	end of discover/rewalk or interface speed update
<code>sched_1m_</code>	every minute
<code>sched_5m_</code>	every five minutes
<code>sched_1h_</code>	every hour
<code>sched_HHMM_</code>	every day at a specific time
<code>web_</code>	triggered by remote HTTP client

After you save the script, AKIPS will check the syntax and notify you of any errors.

13.3 Alerting site scripts

Alerting site scripts supports the following alerts:

- status
- scheduled
- syslog
- threshold
- trap.

To test an alerting site script:

Go to **Admin > API > Site Scripting**.

Enter a hash table of test data for the subroutine you wish to test.

Note the following rules:

Name

The name of the hash table must be identical to the subroutine.

Key-value pairs

Each alert type requires specific key-value pairs.

Each pair must appear on a single line.

AKIPS will interpret undefined pairs as an empty string.

Pairs are delimited by = >

Arrays

Arrays must open and close with [] (square brackets).

Arrays can be either single- or multi-line.

Multi-line arrays must have one value per line.

Values

Values can be either scalar or array.

Closing punctuation

The closing); (parenthesis and semicolon) must be on their own line.

Click **Save**.

From the drop-down menu, select **All alert_ functions**.

Click **Run**.

Examples

Status_

```
our %alert_{foo}_status = (  
  device => "device_value",  
  child  => "child_value",  
  attr   => "attr_value",  
  state  => "state_value",  
);  
  
our %alert_mail_status = (  
  device => "CISCO-82-1-109",  
  child  => "gill1/1",  
  attr   => "IF-MIB.ifOperStatus",  
  state  => "down",  
);
```

Syslog_

```

our %alert_{foo}_syslog = (
    device => "device_value",
    ipaddr => "ipaddr_value",
    msg    => "msg_value",
);

our %alert_mail_syslog = (
    device => "eaton-123-1-190",
    ipaddr => "10.82.0.109",
    msg    => "161 20 1",
);

```

Trap_

```

our %alert_{foo}_trap = (
    device  => "device_value",
    ipaddr  => "ipaddr_value",
    trap_oid => "trap_oid_value",
    uptime  => "uptime_value",
    oids    => [ "oid_1",
                "oid_x",
                "oid_n-1",
                "oid_n" ],
);

our %alert_mail_trap = (
    device  => "cisco-82-0-109",
    ipaddr  => "10.82.0.109",
    trap_oid => "EdgeSwitch-SWITCHING-MIB.
fastPathSwitchingTraps.29",
    uptime  => "1541842604",
    oids    => [ "EdgeSwitch-SWITCHING-MIB.agentLoginSession
                Index: ",
                "EdgeSwitch-SWITCHING-MIB.agentLoginSession
                UserName: akips, ",
                "EdgeSwitch-SWITCHING-MIB.agentLoginSession
                ConnectionType: 3,ssh",
                "EdgeSwitch-SWITCHING-MIB.agentLoginSessionInet
                Address: 10.0.19.2",
                "EdgeSwitch-SWITCHING-MIB.
                agentLoginSessionStatus:1,active" ],
);

```

Index

A

Abbreviations (About this guide), 7
About this guide, 6
adb_flush() (AKIPS database (Perl modules)), 130
adb_result() (AKIPS database (Perl modules)), 130
adb_send() (AKIPS database (Perl modules)), 130
add (Entity commands (Config and events)), 43
add (Event commands (Config and events)), 75
add (Group commands (Config and events)), 58
AKIPS API, 12
AKIPS database (Perl modules), 130
Alerting site scripts, 138
assign (Group commands (Config and events)), 60
Availability, 98

C

calc (Time-series commands (Config and events)), 82
Case study (mcalc (Time-series commands (Config and events))), 83
Case study (mget (Entity commands (Config and events))), 52
Case study (Site scripts), 133
Case study (Web API (Config and events)), 89
clear (Event commands (Config and events)), 76

clear (Group commands (Config and events)), 65
Command console (AKIPS API), 13
Common (Perl modules), 122
Config and events, 43
Configuring groups (Groups (Database overview)), 34
count (Group commands (Config and events)), 66
CSV output (NetFlow reporter), 105
CSV output (NetFlow time series), 110
CSV output (Switch port mapper), 115
CSV output (Unused interfaces), 118
cURL (Web API (Config and events)), 90

D

data (Web API (Config and events)), 91
Database overview, 25
delete (Entity commands (Config and events)), 46
delete (Event commands (Config and events)), 76
delete (Group commands (Config and events)), 67
Device (Availability), 100
Discover (Perl modules), 131
discover_config() (Discover (Perl modules)), 132
discover_device_rewalk() (Discover (Perl modules)), 132

discover_scan() (Discover (Perl modules)), 131

E

Entities (Database overview), 25

Entity commands (Config and events), 43

errlog (Common (Perl modules)), 125

Event commands (Config and events), 74

Events (Availability), 101

Events records (Database overview), 41

G

get (Entity commands (Config and events)), 47

get (Group commands (Config and events)), 68

get_localtime() (Common (Perl modules)), 126

Graphic 1: mapping a hierarchy of groups and super groups, 31

Graphic 2: editing a super group's configuration, 33

Graphic 3: activating the config and events web API, 88

Graphic 4: configuring user settings for the config and events web API, 89

Graphic 5: activating the syslog and traps web API, 97

Graphic 6: configuring user settings for the syslog and traps web API, 97

Graphic 7: activating the NetFlow web API, 107

Graphic 8: configuring user settings for the NetFlow web API, 108

Graphic 9: activating the NetFlow time series web API, 112

Graphic 10: configuring user settings for the NetFlow

time series web API, 113

Graphic 11: activating the switch port mapper web API, 116

Graphic 12: configuring user settings for the switch port mapper web API, 117

Graphic 13: activating the unused interfaces web API, 119

Graphic 14: configuring user settings for the unused interfaces web API, 120

Graphic 15: selecting and copying a site script, 135

Graphic 16: pasting a site script into AKIPS, 135

Group (Availability), 99

Group commands (Config and events), 58

Groups (Database overview), 30

H

http_send() and http_result() (Common (Perl modules)), 129

I

IP address filters (AKIPS API), 23

L

Level 1: parent (Entities (Database overview)), 27

Level 2: child (Entities (Database overview)), 27

Level 3: attribute (Entities (Database overview)), 28

list (Group commands (Config and events)), 69

M

mail() (Common (Perl modules)), 127

mcalc (Time-series commands (Config and events)), 83

mdelete (Entity commands (Config and events)), 49

mdelete (Event commands (Config and events)), 77

- mget (Entity commands (Config and events)), 50
 - mget (Event commands (Config and events)), 78
 - mget (Group commands (Config and events)), 71
 - mget (Time-series commands (Config and events)), 84
 - mlist (Entity commands (Config and events)), 53
 - mlist (Group commands (Config and events)), 71
 - mtype (Entity commands (Config and events)), 55
 - mtype (Group commands (Config and events)), 72
- N**
- Naming a site script, 137
 - NetFlow reporter, 102
 - NetFlow time series, 109
- P**
- Perl modules, 122
 - PRINT_LINE (Common (Perl modules)), 124
 - prune (Group commands (Config and events)), 72
- R**
- Regex (AKIPS API), 14
 - rename (Entity commands (Config and events)), 56
 - rename (Group commands (Config and events)), 73
- S**
- series (Time-series commands (Config and events)), 85
 - set (Entity commands (Config and events)), 57
 - set (Event commands (Config and events)), 80
 - Site scripts, 133
 - Super groups (Groups (Database overview)), 31
 - Switch port mapper, 114
 - Syntax (About this guide), 11
 - Syslog and traps reporter, 92
 - syslog() (Common (Perl modules)), 128
- T**
- TCP socket, 121
 - Test environment (AKIPS API), 12
 - Text conventions (About this guide), 10
 - tf check (Time filters (AKIPS API)), 22
 - tf pairs and tf span (Time filters (AKIPS API)), 19
 - tget (Event commands (Config and events)), 81
 - Time filters (AKIPS API), 15
 - Time series (Database overview), 42
 - Time-series commands (Config and events), 82
 - To activate the config and events web API (Config and events), 88
 - To activate the NetFlow time-series web API, 112
 - To activate the NetFlow web API, 107
 - To activate the switch port mapper web API, 116
 - To activate the syslog and traps web API (Syslog and traps reporter), 96
 - To activate the unused interfaces web API, 119
 - To edit a super group, 32
 - To test an alerting site script, 138
 - To use site scripts, 134
 - To use the command console (AKIPS API), 13
 - To view enumeration and uptime attributes (Events records (Database overview)), 41
 - To view error messages (Common (Perl modules)), 125

To view threshold attributes
 (Events records (Database
 overview)), 41
top (Time-series commands (Config
 and events)), 86
trim (Common (Perl modules)), 124

U

Unused interfaces, 118
Useful arrays (Common (Perl
 modules)), 123
Using site scripts, 134

V

Virtual attributes (Entities
 (Database overview)), 29

W

Web API (Config and events), 87
Web API (NetFlow reporter), 106
Web API (NetFlow time series), 111
Web API (Switch port mapper), 116
Web API (Unused interfaces), 119